



# Magnitude Simba Apache Hive ODBC Data Connector

## Installation and Configuration Guide

Version 2.6.11  
March 26, 2021

**Copyright © 2021 Magnitude Software, Inc. All rights reserved.**

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without prior written permission from Magnitude.

The information in this document is subject to change without notice. Magnitude strives to keep this information accurate but does not warrant that this document is error-free.

Any Magnitude product described herein is licensed exclusively subject to the conditions set forth in your Magnitude license agreement.

Simba, the Simba logo, SimbaEngine, and Simba Technologies are registered trademarks of Simba Technologies Inc. in Canada, the United States and/or other countries. All other trademarks and/or servicemarks are the property of their respective owners.

All other company and product names mentioned herein are used for identification purposes only and may be trademarks or registered trademarks of their respective owners.

Information about the third-party products is contained in a third-party-licenses.txt file that is packaged with the software.

## **Contact Us**

Magnitude Software, Inc.

[www.magnitude.com](http://www.magnitude.com)

## About This Guide

### Purpose

The *Magnitude Simba Apache Hive ODBC Data Connector Installation and Configuration Guide* explains how to install and configure the Magnitude Simba Apache Hive ODBC Data Connector. The guide also provides details related to features of the connector.

### Audience

The guide is intended for end users of the Simba Apache Hive ODBC Connector, as well as administrators and developers integrating the connector.

### Knowledge Prerequisites

To use the Simba Apache Hive ODBC Connector, the following knowledge is helpful:

- Familiarity with the platform on which you are using the Simba Apache Hive ODBC Connector
- Ability to use the data source to which the Simba Apache Hive ODBC Connector is connecting
- An understanding of the role of ODBC technologies and driver managers in connecting to a data source
- Experience creating and configuring ODBC connections
- Exposure to SQL

### Document Conventions

*Italics* are used when referring to book and document titles.

**Bold** is used in procedures for graphical user interface elements that a user clicks and text that a user types.

Monospace font indicates commands, source code, or contents of text files.

#### Note:

A text box with a pencil icon indicates a short note appended to a paragraph.

**! Important:**

A text box with an exclamation mark indicates an important comment related to the preceding paragraph.

# Table of Contents

About the Simba Apache Hive ODBC Connector .....	7
Windows Connector .....	8
Windows System Requirements .....	8
Installing the Connector on Windows .....	8
Creating a Data Source Name on Windows .....	9
Configuring a DSN-less Connection on Windows .....	12
Configuring Authentication on Windows .....	15
Configuring Advanced Options on Windows .....	21
Configuring a Proxy Connection on Windows .....	23
Configuring HTTP Options on Windows .....	24
Configuring SSL Verification on Windows .....	25
Configuring Server-Side Properties on Windows .....	26
Configuring Logging Options on Windows .....	28
Configuring Kerberos Authentication for Windows .....	31
Verifying the Connector Version Number on Windows .....	35
macOS Connector .....	37
macOS System Requirements .....	37
Installing the Connector on macOS .....	37
Verifying the Connector Version Number on macOS .....	38
Linux Connector .....	39
Linux System Requirements .....	39
Installing the Connector Using the RPM File .....	40
Installing the Connector Using the Tarball Package .....	41
Installing the Connector on Debian .....	42
Verifying the Connector Version Number on Linux .....	43
AIX Connector .....	44
AIX System Requirements .....	44
Installing the Connector on AIX .....	44
Verifying the Connector Version Number on AIX .....	45
Solaris Connector .....	46
Solaris System Requirements .....	46
Installing the Connector on Solaris .....	46
Verifying the Connector Version Number on Solaris .....	47

- Configuring the ODBC Driver Manager on Non-Windows Machines ..... 48
  - Specifying ODBC Driver Managers on Non-Windows Machines ..... 48
  - Specifying the Locations of the Connector Configuration Files ..... 49
- Configuring ODBC Connections on a Non-Windows Machine ..... 51
  - Creating a Data Source Name on a Non-Windows Machine ..... 51
  - Configuring a DSN-less Connection on a Non-Windows Machine ..... 55
  - Configuring Service Discovery Mode on a Non-Windows Machine ..... 57
  - Configuring Authentication on a Non-Windows Machine ..... 58
  - Configuring SSL Verification on a Non-Windows Machine ..... 62
  - Configuring Server-Side Properties on a Non-Windows Machine ..... 63
  - Configuring Logging Options on a Non-Windows Machine ..... 64
  - Setting Connector-Wide Configuration Options on a Non-Windows Machine ..... 66
  - Testing the Connection on a Non-Windows Machine ..... 67
- Authentication Mechanisms ..... 69
- Using a Connection String ..... 71
  - DSN Connection String Example ..... 71
  - DSN-less Connection String Examples ..... 71
- Features ..... 75
  - SQL Connector for HiveQL ..... 75
  - Data Types ..... 76
  - Catalog and Schema Support ..... 77
  - hive\_system Table ..... 77
  - Server-Side Properties ..... 78
  - Get Tables With Query ..... 78
  - Active Directory ..... 78
  - Write-back ..... 79
  - Timestamp Function Support ..... 79
  - Dynamic Service Discovery using ZooKeeper ..... 79
  - Security and Authentication ..... 80
- Connector Configuration Options ..... 81
  - Configuration Options Appearing in the User Interface ..... 81
  - Configuration Options Having Only Key Names ..... 110
- Third-Party Trademarks ..... 116

## About the Simba Apache Hive ODBC Connector

The Simba Apache Hive ODBC Connector is used for direct SQL and HiveQL access to Apache Hadoop / Hive distributions, enabling Business Intelligence (BI), analytics, and reporting on Hadoop / Hive-based data. The connector efficiently transforms an application's SQL query into the equivalent form in HiveQL, which is a subset of SQL-92. If an application is Hive-aware, then the connector is configurable to pass the query through to the database for processing. The connector interrogates Hive to obtain schema information to present to a SQL-based application. Queries, including joins, are translated from SQL to HiveQL. For more information about the differences between HiveQL and SQL, see [SQL Connector for HiveQL](#) on page 75.

The Simba Apache Hive ODBC Connector complies with the ODBC 3.80 data standard and adds important functionality such as Unicode and 32- and 64-bit support for high-performance computing environments.

ODBC is one of the most established and widely supported APIs for connecting to and working with databases. At the heart of the technology is the ODBC connector, which connects an application to the database. For more information about ODBC, see *Data Access Standards* on the Simba Technologies website: <https://www.simba.com/resources/data-access-standards-glossary>. For complete information about the ODBC specification, see the *ODBC API Reference* from the Microsoft documentation: <https://docs.microsoft.com/en-us/sql/odbc/reference/syntax/odbc-api-reference>.

The Simba Apache Hive ODBC Connector is available for Microsoft® Windows®, Linux, Solaris, AIX, and macOS platforms.

The *Installation and Configuration Guide* is suitable for users who are looking to access data residing within Hive from their desktop environment. Application developers might also find the information helpful. Refer to your application for details on connecting via ODBC.

### Note:

For basic configuration instructions that allow you to quickly set up the Windows connector so that you can evaluate and use it, see the *Simba ODBC Connectors Quick Start Guide for Windows*. The Quick Start Guide also explains how to use the connector in various applications.

# Windows Connector

## Windows System Requirements

The Simba Apache Hive ODBC Connector supports Apache Hive versions 1.0.0 through 3.1.0.

Install the connector on client machines where the application is installed. Before installing the connector, make sure that you have the following:

- Administrator rights on your machine.
- A machine that meets the following system requirements:
  - One of the following operating systems:
    - Windows 10, 8.1, or 7 SP1
    - Windows Server 2016, 2012, or 2008 R2 SP1
  - 100 MB of available disk space

Before the connector can be used, the Visual C++ Redistributable for Visual Studio 2013 with the same bitness as the connector must also be installed. If you obtained the connector from the Simba website, then your installation of the connector automatically includes this dependency. Otherwise, you must install the redistributable manually. You can download the installation packages for the redistributable at <https://www.microsoft.com/en-ca/download/details.aspx?id=40784>.

## Installing the Connector on Windows

If you did not obtain this connector from the Simba website, you might need to follow a different installation procedure. For more information, see the *Simba OEM ODBC Connectors Installation Guide*.

On 64-bit Windows operating systems, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit connectors, and 32-bit applications must use 32-bit connectors. Make sure that you use a connector whose bitness matches the bitness of the client application:

- `SimbaHiveODBC32.msi` for 32-bit applications
- `SimbaHiveODBC64.msi` for 64-bit applications

You can install both versions of the connector on the same machine.



**To install the Simba Apache Hive ODBC Connector on Windows:**

1. Depending on the bitness of your client application, double-click to run **SimbaHiveODBC32.msi** or **SimbaHiveODBC64.msi**.
2. Click **Next**.
3. Select the check box to accept the terms of the License Agreement if you agree, and then click **Next**.
4. To change the installation location, click **Change**, then browse to the desired folder, and then click **OK**. To accept the installation location, click **Next**.
5. Click **Install**.
6. When the installation completes, click **Finish**.
7. If you received a license file through email, then copy the license file into the `\lib` subfolder of the installation folder you selected above. You must have Administrator privileges when changing the contents of this folder.

## Creating a Data Source Name on Windows


Typically, after installing the Simba Apache Hive ODBC Connector, you need to create a Data Source Name (DSN). A DSN is a data structure that stores connection information so that it can be used by the connector to connect to Hive.

Alternatively, you can specify connection settings in a connection string or as connector-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

The following instructions describe how to create a DSN. For information about specifying settings in a connection string, see [Using a Connection String](#) on page 71. For information about connector-wide settings, see [Configuring a DSN-less Connection on Windows](#) on page 12.

**To create a Data Source Name on Windows:**


1. From the Start menu, go to **ODBC Data Sources**.

 **Note:**

Make sure to select the ODBC Data Source Administrator that has the same bitness as the client application that you are using to connect to Hive.

2. In the ODBC Data Source Administrator, click the **Drivers** tab, and then scroll down as needed to confirm that the Simba Apache Hive ODBC Connector appears in the alphabetical list of ODBC connectors that are installed on your system.
3. Choose one:

- To create a DSN that only the user currently logged into Windows can use, click the **User DSN** tab.
- Or, to create a DSN that all users who log into Windows can use, click the **System DSN** tab.

 **Note:**

It is recommended that you create a System DSN instead of a User DSN. Some applications load the data using a different user account, and might not be able to detect User DSNs that are created under another user account.

4. Click **Add**.
5. In the Create New Data Source dialog box, select **Simba Apache Hive ODBC Connector** and then click **Finish**. The Simba Apache Hive ODBC Connector DSN Setup dialog box opens.
6. In the **Data Source Name** field, type a name for your DSN.
7. Optionally, in the **Description** field, type relevant details about the DSN.
8. In the **Hive Server Type** drop-down list, select **Hive Server 1** or **Hive Server 2**.

 **Note:**

If you are connecting through Apache ZooKeeper, then **Hive Server 1** is not supported.

9. Specify whether the connector uses the ZooKeeper service when connecting to Hive, and provide the necessary connection information:
  - To connect to Hive without using the Apache ZooKeeper service, do the following:
    - a. From the **Service Discovery Mode** drop-down list, select **No Service Discovery**.
    - b. In the **Host(s)** field, type the IP address or host name of the Hive server.
    - c. In the **Port** field, type the number of the TCP port that the Hive server uses to listen for client connections.
  - Or, to discover Hive Server 2 services via the ZooKeeper service, do the following:
    - a. From the **Service Discovery Mode** drop-down list, select **ZooKeeper**.
    - b. In the **Host(s)** field, type a comma-separated list of ZooKeeper servers. Use the following format, where *[ZK\_Host]* is the IP address or host name of the ZooKeeper server and *[ZK\_Port]* is the number of the TCP port that the ZooKeeper server uses to listen for client connections:

```
[ZK_Host1]:[ZK_Port1],[ZK_Host2]:[ZK_Port2]
```

- c. In the **ZooKeeper Namespace** field, type the namespace on ZooKeeper under which Hive Server 2 znodes are added.
10. In the **Database** field, type the name of the database schema to use when a schema is not explicitly specified in a query.

 **Note:**


You can still issue queries on other schemas by explicitly specifying the schema in the query. To inspect your databases and determine the appropriate schema to use, type the `show databases` command at the Hive command prompt.

11. In the Authentication area, configure authentication as needed. For more information, see [Configuring Authentication on Windows](#) on page 15.

 **Note:**

Hive Server 1 does not support authentication. Most default configurations of Hive Server 2 require User Name authentication. To verify the authentication mechanism that you need to use for your connection, check the configuration of your Hadoop / Hive distribution. For more information, see [Authentication Mechanisms](#) on page 69.

12. Optionally, if the operations against Hive are to be done on behalf of a user that is different than the authenticated user for the connection, type the name of the user to be delegated in the **Delegation UID** field. For more information, see [Delegating Authentication to a Specific User](#) on page 20.

 **Note:**

This option is applicable only when connecting to a Hive Server 2 instance that supports this feature.


13. In the **Thrift Transport** drop-down list, select the transport protocol to use in the Thrift layer.

 **Note:**

For information about how to determine which Thrift transport protocols your Hive server supports, see [Authentication Mechanisms](#) on page 69.


14. If the Thrift Transport option is set to HTTP, then to configure HTTP options such as custom headers, click **HTTP Options**. For more information, see [Configuring HTTP Options on Windows](#) on page 24.

15. To configure the connector to connect to Hive through a proxy server, click **Proxy Options**. For more information, see [Configuring a Proxy Connection on Windows](#) on page 23.
16. To configure client-server verification over SSL, click **SSL Options**. For more information, see [Configuring SSL Verification on Windows](#) on page 25.

 **Note:**

If you selected User Name as the authentication mechanism, SSL is not available.

17. To configure advanced connector options, click **Advanced Options**. For more information, see [Configuring Advanced Options on Windows](#) on page 21.
18. To configure server-side properties, click **Advanced Options** and then click **Server Side Properties**. For more information, see [Configuring Server-Side Properties on Windows](#) on page 26.
19. To configure logging behavior for the connector, click **Logging Options**. For more information, see [Configuring Logging Options on Windows](#) on page 28.
20. To test the connection, click **Test**. Review the results as needed, and then click **OK**.

 **Note:**


If the connection fails, then confirm that the settings in the Simba Hive ODBC Driver DSN Setup dialog box are correct. Contact your Hive server administrator as needed.

21. To save your settings and close the Simba Hive ODBC Driver DSN Setup dialog box, click **OK**.
22. To close the ODBC Data Source Administrator, click **OK**.

## Configuring a DSN-less Connection on Windows

Some client applications provide support for connecting to a data source using a connector without a Data Source Name (DSN). To configure a DSN-less connection, you can use a connection string or the Simba Hive ODBC Driver Configuration tool that is installed with the Simba Apache Hive ODBC Connector. Settings in a connection string apply only when you connect to Hive using that particular string, while settings in the connector configuration tool apply to every connection that uses the Simba Apache Hive ODBC Connector.


The following section explains how to use the connector configuration tool. For information about using connection strings, see [Using a Connection String](#) on page 71.

 **Note:**

- Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.
- The drop-down lists in the connector configuration tool only display one option at a time. Use the scroll arrows on the right side of the drop-down list to view and select other options.

**To configure a DSN-less connection using the connector configuration tool:**

## 1. Choose one:

- If you are using Windows 7 or earlier, click **Start**  > **All Programs > Simba Apache Hive ODBC Connector 2.6 > Driver Configuration**.
- Or, if you are using Windows 8 or later, click the arrow button at the bottom of the Start screen, and then click **Simba Apache Hive ODBC Connector 2.6 > Driver Configuration**.

 **Note:**

Make sure to select the Driver Configuration Tool that has the same bitness as the client application that you are using to connect to Hive.

2. If you are prompted for administrator permission to make modifications to the machine, click **OK**. **Note:**

You must have administrator access to the machine to run this application because it makes changes to the registry.

3. In the **Hive Server Type** drop-down list, select **Hive Server 1** or **Hive Server 2**. **Note:**

If you are connecting through Apache ZooKeeper, then **Hive Server 1** is not supported.


## 4. Specify whether the connector uses the ZooKeeper service when connecting to Hive:

- To connect to Hive without using the Apache ZooKeeper service, from the **Service Discovery Mode** drop-down list, select **No Service Discovery**.
- Or, to discover Hive Server 2 services via the ZooKeeper service, do the following:
  - a. From the **Service Discovery Mode** drop-down list, select **ZooKeeper**.
  - b. In the **Host(s)** field, type a comma-separated list of ZooKeeper servers. Use the following format, where *[ZK\_Host]* is the IP address

or host name of the ZooKeeper server and *[ZK\_Port]* is the number of the TCP port that the ZooKeeper server uses to listen for client connections:

```
[ZK_Host1]:[ZK_Port1],[ZK_Host2]:[ZK_Port2]
```

- c. In the **ZooKeeper Namespace** field, type the namespace on ZooKeeper under which Hive Server 2 znodes are added.
5. In the Authentication area, configure authentication as needed. For more information, see [Configuring Authentication on Windows](#) on page 15.

 **Note:**

Hive Server 1 does not support authentication. Most default configurations of Hive Server 2 require User Name authentication. To verify the authentication mechanism that you need to use for your connection, check the configuration of your Hadoop / Hive distribution. For more information, see [Authentication Mechanisms](#) on page 69.

6. Optionally, if the operations against Hive are to be done on behalf of a user that is different than the authenticated user for the connection, then in the **Delegation UID** field, type the name of the user to be delegated. For more information, see [Delegating Authentication to a Specific User](#) on page 20.

 **Note:**


This option is applicable only when connecting to a Hive Server 2 instance that supports this feature.

7. In the **Thrift Transport** drop-down list, select the transport protocol to use in the Thrift layer.

 **Note:**

For information about how to determine which Thrift transport protocols your Hive server supports, see [Authentication Mechanisms](#) on page 69.

8. If the Thrift Transport option is set to HTTP, then to configure HTTP options such as custom headers, click **HTTP Options**. For more information, see [Configuring HTTP Options on Windows](#) on page 24.
9. To configure the connector to connect to Hive through a proxy server, click **Proxy Options**. For more information, see [Configuring a Proxy Connection on Windows](#) on page 23.
10. To configure client-server verification over SSL, click **SSL Options**. For more information, see [Configuring SSL Verification on Windows](#) on page 25.

 **Note:**

If you selected User Name as the authentication mechanism, SSL is not available.

11. To configure advanced options, click **Advanced Options**. For more information, see [Configuring Advanced Options on Windows](#) on page 21.
12. To configure server-side properties, click **Advanced Options** and then click **Server Side Properties**. For more information, see [Configuring Server-Side Properties on Windows](#) on page 26.
13. To save your settings and close the Simba Hive ODBC Driver Configuration tool, click **OK**.

## Configuring Authentication on Windows

Some Hive Server 2 instances are configured to require authentication for access. To connect to a Hive server, you must configure the Simba Apache Hive ODBC Connector to use the authentication mechanism that matches the access requirements of the server and provides the necessary credentials.

For information about how to determine the type of authentication your Hive server requires, see [Authentication Mechanisms](#) on page 69.

You can specify authentication settings in a DSN, in a connection string, or as connector-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

If cookie-based authentication is enabled in your Hive Server 2 database, you can specify a list of authentication cookies in the `HTTPAuthCookies` connection property. In this case, the connector authenticates the connection once based on the provided authentication credentials. It then uses the cookie generated by the server for each subsequent request in the same connection. For more information, see [HTTPAuthCookies](#) on page 112.

 **Note:**

On Windows, the `HTTPAuthCookies` property must be set in a connection string.

## Using No Authentication

When connecting to a Hive server of type Hive Server 1, you must use No Authentication. When you use No Authentication, Binary is the only Thrift transport protocol that is supported.

**To configure a connection without authentication:**

1. Choose one:
  - To access authentication options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
  - Or, to access authentication options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool.
2. From the **Mechanism** drop-down list, select **No Authentication**.
3. If the Hive server is configured to use SSL, then click **SSL Options** to configure SSL for the connection. For more information, see [Configuring SSL Verification on Windows](#) on page 25.
4. To save your settings and close the dialog box, click **OK**.

## Using Kerberos


This authentication mechanism is available only for Hive Server 2 on non-HDInsight distributions. When you use Kerberos authentication, the Binary transport protocol is not supported.

If the Use Only SSPI advanced option is disabled, then Kerberos must be installed and configured before you can use this authentication mechanism. For information about configuring Kerberos on your machine, see [Configuring Kerberos Authentication for Windows](#) on page 31. For information about setting the Use Only SSPI advanced option, see [Configuring Advanced Options on Windows](#) on page 21.

**To configure Kerberos authentication:**

1. Choose one:
  - To access authentication options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
  - Or, to access authentication options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool.
2. From the **Mechanism** drop-down list, select **Kerberos**.
3. Choose one:
  - To use the default realm defined in your Kerberos setup, leave the **Realm** field empty.
  - Or, if your Kerberos setup does not define a default realm or if the realm of your Hive Server 2 host is not the default, then, in the **Realm** field, type the Kerberos realm of the Hive Server 2.
4. In the **Host FQDN** field, type the fully qualified domain name of the Hive Server 2 host.



 **Note:**

To use the Hive server host name as the fully qualified domain name for Kerberos authentication, in the **Host FQDN** field, type **\_HOST**.

5. In the **Service Name** field, type the service name of the Hive server.
6. Optionally, if you are using MIT Kerberos and a Kerberos realm is specified in the **Realm** field, then choose one:
  - To have the Kerberos layer canonicalize the server's service principal name, leave the **Canonicalize Principal FQDN** check box selected.
  - Or, to prevent the Kerberos layer from canonicalizing the server's service principal name, clear the **Canonicalize Principal FQDN** check box.
7. To allow the connector to pass your credentials directly to the server for use in authentication, select **Delegate Kerberos Credentials**.
8. From the **Thrift Transport** drop-down list, select the transport protocol to use in the Thrift layer.

 **Important:**

When using this authentication mechanism, the Binary transport protocol is not supported.

9. If the Hive server is configured to use SSL, then click **SSL Options** to configure SSL for the connection. For more information, see [Configuring SSL Verification on Windows](#) on page 25.
10. To save your settings and close the dialog box, click **OK**.

## Using SAML 2.0

This authentication mechanism enables you to authenticate via Single Sign-On using SAML 2.0 against supported servers.


 **Important:**

In order to use SAML 2.0 for authentication, Thrift Transport must be set to HTTP and SSL must be enabled.

### To configure SAML 2.0 authentication:

1. To access authentication options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
2. In the **Mechanism** drop-down list, select **SAML\_2.0**.
3. In the **Host** field, type the fully qualified domain name of the Hive server host.

4. In the **Port** field, type the number of the TCP port that the Hive server uses to listen for client connections.
5. Optionally, in the **Transport Buffer Size** field, type the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

6. In the **Thrift Transport** drop-down list, select **HTTP**.
7. Optionally, click **SAML Options** and select the **Ignore SQL\_DRIVER\_NOPROMPT** check box. When the application is making a `SQLDriverConnect` call with a `SQL_DRIVER_NOPROMPT` flag, this option displays the web browser used to complete the browser based authentication flow.
8. Click **HTTP Options** and in the **HTTP Path** field, type the partial URL corresponding to the Hive server. For more information, see [Configuring HTTP Options on Windows](#) on page 24.
9. Click **SSL Options** and select the **Enable SSL** check box. For more information, see [Configuring SSL Verification on Windows](#) on page 25
10. To save your settings and close the dialog box, click **OK**.

## Using User Name

This authentication mechanism requires a user name but not a password. The user name labels the session, facilitating database tracking.

This authentication mechanism is available only for Hive Server 2 on non-HDInsight distributions. Most default configurations of Hive Server 2 require User Name authentication. When you use User Name authentication, SSL is not supported and SASL is the only Thrift transport protocol available.

### To configure User Name authentication:

1. Choose one:
  - To access authentication options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
  - Or, to access authentication options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool.
2. From the **Mechanism** drop-down list, select **User Name**.
3. In the **User Name** field, type an appropriate user name for accessing the Hive server.
4. To save your settings and close the dialog box, click **OK**.

## Using User Name And Password

This authentication mechanism requires a user name and a password.

This authentication mechanism is available only for Hive Server 2 on non-HDInsight distributions.

### To configure User Name And Password authentication:

1. Choose one:
  - To access authentication options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
  - Or, to access authentication options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool.
2. From the **Mechanism** drop-down list, select **User Name And Password**.
3. In the **User Name** field, type an appropriate user name for accessing the Hive server.
4. In the **Password** field, type the password corresponding to the user name you typed above.
5. To save the password, select the **Save Password (Encrypted)** check box.

#### ! Important:

The password is obscured, that is, not saved in plain text. However, it is still possible for the encrypted password to be copied and used.

6. From the **Thrift Transport** drop-down list, select the transport protocol to use in the Thrift layer.
7. If the Hive server is configured to use SSL, then click **SSL Options** to configure SSL for the connection. For more information, see [Configuring SSL Verification on Windows](#) on page 25.
8. To save your settings and close the dialog box, click **OK**.

## Using Windows Azure HDInsight Service

This authentication mechanism is available only for Hive Server 2 on HDInsight distributions. When you use this authentication mechanism, you must enable SSL and HTTP is the only Thrift transport protocol available.

### To configure a connection to a Hive server on Windows Azure HDInsight Service:

1. Choose one:
  - To access authentication options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then

click **Configure**.

- Or, to access authentication options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool.
2. From the **Mechanism** drop-down list, select **Windows Azure HDInsight Service**.
  3. In the **User Name** field, type an appropriate user name for accessing the Hive server.
  4. In the **Password** field, type the password corresponding to the user name you typed above.
  5. To save the password, select the **Save Password (Encrypted)** check box.

**! Important:**

The password is obscured, that is, not saved in plain text. However, it is still possible for the encrypted password to be copied and used.

6. Click **HTTP Options**, and in the **HTTP Path** field, type the partial URL corresponding to the Hive server. Click **OK** to save your HTTP settings and close the dialog box.

 **Note:**

If necessary, you can create custom HTTP headers. For more information, see [Configuring HTTP Options on Windows](#) on page 24.

7. Click **SSL Options** and configure SSL settings as needed. For more information, see [Configuring SSL Verification on Windows](#) on page 25.
8. Click **OK** to save your SSL configuration and close the dialog box, and then click **OK** to save your authentication settings and close the dialog box.

## Delegating Authentication to a Specific User

Some Hive Server 2 instances support the ability to delegate all operations against Hive to the specified user, rather than to the authenticated user for the connection.

### To delegate all operations to a specified user:

1. Choose one:
  - To access authentication options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
  - Or, to access authentication options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool.
2. In the **Delegation UID** field, type the name of the user to be delegated.
3. To save your settings and close the dialog box, click **OK**.

If the server returns an error message such as **Failed to validate proxy privilege of *[RealUser]* for *[DelegationUID]***, you may need to modify the server's `core-site.xml` configuration file, as follows:

1. In the server's `core-site.xml` configuration file, add the following properties:

```
hadoop.proxyuser.[RealUser].groups=*
hadoop.proxyuser.[RealUser].hosts=*
```

Where *[RealUser]* is the authenticated user for the connection.

2. If you are using Kerberos authentication, then in the server's `core-site.xml` configuration file, add the following properties:

```
hadoop.proxyuser.[Principal].groups=*
hadoop.proxyuser.[Principal].hosts=*
```

Where *[Principal]* is the primary Kerberos principal user. For example, if the primary Kerberos principal user is `kerbuser@example.com`, replace *[Principal]* with `kerbuser`.

For more information on resolving this error, see your Hive Server documentation.

## Configuring Advanced Options on Windows

You can configure advanced options to modify the behavior of the connector.

The following instructions describe how to configure advanced options in a DSN and in the connector configuration tool. You can specify the connection settings described below in a DSN, in a connection string, or as connector-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.


**To configure advanced options on Windows:**

1. Choose one:
  - To access advanced options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Advanced Options**.
  - Or, to access advanced options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool, and then click **Advanced Options**.
2. To disable the SQL Connector feature, select the **Use Native Query** check box.

**! Important:**

- When this option is enabled, the connector cannot execute parameterized queries.
- By default, the connector applies transformations to the queries emitted by an application to convert the queries into an equivalent form in HiveQL. If the application is Hive-aware and already emits HiveQL, then turning off the translation avoids the additional overhead of query transformation.

3. To defer query execution to SQLExecute, select the **Fast SQLPrepare** check box.
4. To allow connector-wide configurations to take precedence over connection and DSN settings, select the **Driver Config Take Precedence** check box.
5. To use the asynchronous version of the API call against Hive for executing a query, select the **Use Async Exec** check box.
6. To retrieve table names from the database by using the SHOW TABLES query, select the **Get Tables With Query** check box.

 **Note:**

This option is applicable only when connecting to Hive Server 2.

7. To enable the connector to return SQL\_WVARCHAR instead of SQL\_VARCHAR for STRING and VARCHAR columns, and SQL\_WCHAR instead of SQL\_CHAR for CHAR columns, select the Unicode SQL Character Types check box.
8. To enable the connector to return the hive\_system table for catalog function calls such as SQLTables and SQLColumns, select the **Show System Table** check box.
9. To specify which mechanism the connector uses by default to handle Kerberos authentication, do one of the following:
  - To use the SSPI plugin by default, select the **Use Only SSPI** check box.
  - To use MIT Kerberos by default and only use the SSPI plugin if the GSSAPI library is not available, clear the **Use Only SSPI** check box.
10. To enable the connector to automatically open a new session when the existing session is no longer valid, select the **Invalid Session Auto Recover** check box.

 **Note:**

This option is applicable only when connecting to Hive Server 2.

11. To have the connector automatically attempt to reconnect to the server if communications are lost, select **Enable Auto Reconnect**.

12. In the **Rows Fetched Per Block** field, type the number of rows to be fetched per block.
13. In the **Max Bytes Per Fetch Request** field, type the maximum number of bytes to be fetched.

 **Note:**

- This option is applicable only when connecting to a server that supports result set data serialized in arrow format.
- The value must be specified in one of the following:
  - B (bytes)
  - KB (kilobytes)
  - MB (megabytes)
  - GB (gigabytes)


By default, the file size is in B (bytes).

14. In the **Default String Column Length** field, type the maximum data length for STRING columns.
15. In the **Binary Column Length** field, type the maximum data length for BINARY columns.
16. In the **Decimal Column Scale** field, type the maximum number of digits to the right of the decimal point for numeric data types.
17. In the **Async Exec Poll Interval** field, type the time in milliseconds between each poll for the query execution status.

 **Note:**

This option is applicable only to HDInsight clusters.

18. In the **Socket Timeout** field, type the number of seconds that an operation can remain idle before it is closed.

 **Note:**

This option is applicable only when asynchronous query execution is being used against Hive Server 2 instances.

19. To save your settings and close the Advanced Options dialog box, click **OK**.

## Configuring a Proxy Connection on Windows

If you are connecting to the data source through a proxy server, you must provide connection information for the proxy server.

### To configure a proxy server connection on Windows:

1. To access proxy server options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Proxy Options**.
2. In the **Proxy Host** field, type the host name or IP address of the proxy server.
3. In the **Proxy Port** field, type the number of the TCP port that the proxy server uses to listen for client connections.
4. In the **Proxy Username** field, type your user name for accessing the proxy server.
5. In the **Proxy Password** field, type the password corresponding to the user name.
6. To save your settings and close the Proxy Options dialog box, click **OK**.


## Configuring HTTP Options on Windows

You can configure options such as custom headers when using the HTTP transport protocol in the Thrift layer. For information about how to determine if your Hive server supports the HTTP transport protocol, see [Authentication Mechanisms](#) on page 69.

The following instructions describe how to configure HTTP options in a DSN and in the connector configuration tool. You can specify the connection settings described below in a DSN, in a connection string, or as connector-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

### To configure HTTP options on Windows:

1. Choose one:
  - If you are configuring HTTP for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then make sure that the Thrift Transport option is set to **HTTP**.
  - Or, if you are configuring HTTP for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool and then make sure that the Thrift Transport option is set to **HTTP**.
2. To access HTTP options, click **HTTP Options**.

 **Note:**

The HTTP options are available only when the Thrift Transport option is set to HTTP.

3. In the **HTTP Path** field, type the partial URL corresponding to the Hive server.
4. To create a custom HTTP header, click **Add**, then type appropriate values in the **Key** and **Value** fields, and then click **OK**.



5. To edit a custom HTTP header, select the header from the list, then click **Edit**, then update the **Key** and **Value** fields as needed, and then click **OK**.
6. To delete a custom HTTP header, select the header from the list, and then click **Remove**. In the confirmation dialog box, click **Yes**.
7. To save your settings and close the HTTP Properties dialog box, click **OK**.

## Configuring SSL Verification on Windows

If you are connecting to a Hive server that has Secure Sockets Layer (SSL) enabled, you can configure the connector to connect to an SSL-enabled socket. When using SSL to connect to a server, the connector supports identity verification between the client (the connector itself) and the server.

The following instructions describe how to configure SSL in a DSN and in the connector configuration tool. You can specify the connection settings described below in a DSN, in a connection string, or as connector-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

### Note:

If you selected User Name as the authentication mechanism, SSL is not available.

### To configure SSL verification on Windows:

1. Choose one:
  - To access SSL options for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **SSL Options**.
  - Or, to access advanced options for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool, and then click **SSL Options**.
2. Select the **Enable SSL** check box.
3. To allow authentication using self-signed certificates that have not been added to the list of trusted certificates, select the **Allow Self-signed Server Certificate** check box.
4. To allow the common name of a CA-issued SSL certificate to not match the host name of the Hive server, select the **Allow Common Name Host Name Mismatch** check box.
5. To specify the CA certificates that you want to use to verify the server, do one of the following:
  - To verify the server using the trusted CA certificates from a specific `.pem` file, specify the full path to the file in the **Trusted Certificates** field and clear the **Use System Trust Store** check box.

- Or, to use the trusted CA certificates `.pem` file that is installed with the connector, leave the **Trusted Certificates** field empty, and clear the **Use System Trust Store** check box.
- Or, to use the Windows trust store, select the **Use System Trust Store** check box.

**! Important:**

- If you are using the Windows trust store, make sure to import the trusted CA certificates into the trust store.
- If the trusted CA supports certificate revocation, select the **Check Certificate Revocation** check box.

6. From the **Minimum TLS Version** drop-down list, select the minimum version of TLS to use when connecting to your data store.
7. To configure two-way SSL verification, select the **Two-Way SSL** check box and then do the following:
  - a. In the **Client Certificate File** field, specify the full path of the PEM file containing the client's certificate.
  - b. In the **Client Private Key File** field, specify the full path of the file containing the client's private key.
  - c. If the private key file is protected with a password, type the password in the **Client Private Key Password** field. To save the password, select the **Save Password (Encrypted)** check box.

**! Important:**

The password is obscured, that is, not saved in plain text. However, it is still possible for the encrypted password to be copied and used.

8. To save your settings and close the SSL Options dialog box, click **OK**.


## Configuring Server-Side Properties on Windows

You can use the connector to apply configuration properties to the Hive server.

The following instructions describe how to configure server-side properties in a DSN and in the connector configuration tool. You can specify the connection settings described below in a DSN, in a connection string, or as connector-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

**To configure server-side properties on Windows:**

1. Choose one:
  - To configure server-side properties for a DSN, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, then click **Advanced Options**, and then click **Server Side Properties**.
  - Or, to configure server-side properties for a DSN-less connection, open the Simba Hive ODBC Driver Configuration tool, then click **Advanced Options**, and then click **Server Side Properties**.
2. To create a server-side property, click **Add**, then type appropriate values in the **Key** and **Value** fields, and then click **OK**. For example, to set the value of the `mapreduce.job.queueName` property to `myQueue`, type **mapreduce.job.queueName** in the **Key** field and then type **myQueue** in the **Value** field.

 **Note:**

For a list of all Hadoop and Hive server-side properties that your implementation supports, type `set -v` at the Hive CLI command line or Beeline. You can also execute the `set -v` query after connecting using the connector.

3. To edit a server-side property, select the property from the list, then click **Edit**, then update the **Key** and **Value** fields as needed, and then click **OK**.
4. To delete a server-side property, select the property from the list, and then click **Remove**. In the confirmation dialog box, click **Yes**.
5. To configure the connector to convert server-side property key names to all lower-case characters, select the **Convert Key Name To Lower Case** check box.
6. To change the method that the connector uses to apply server-side properties, do one of the following:
  - To configure the connector to apply each server-side property by executing a query when opening a session to the Hive server, select the **Apply Server Side Properties With Queries** check box.
  - Or, to configure the connector to use a more efficient method for applying server-side properties that does not involve additional network round-tripping, clear the **Apply Server Side Properties With Queries** check box.

 **Note:**

The more efficient method is not available for Hive Server 1, and it might not be compatible with some Hive Server 2 builds. If the server-side properties do not take effect when the check box is clear, then select the check box.

7. To save your settings and close the Server Side Properties dialog box, click **OK**.

## Configuring Logging Options on Windows

To help troubleshoot issues, you can enable logging. In addition to functionality provided in the Simba Apache Hive ODBC Connector, the ODBC Data Source Administrator provides tracing functionality.

### ! Important:

Only enable logging or tracing long enough to capture an issue. Logging or tracing decreases performance and can consume a large quantity of disk space.

### Configuring Connector-wide Logging Options

The settings for logging apply to every connection that uses the Simba Apache Hive ODBC Connector, so make sure to disable the feature after you are done using it. To configure logging for the current connection, see [Configuring Logging for the Current Connection](#) on page 30.

#### To enable connector-wide logging on Windows:

1. To access logging options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Logging Options**.
2. From the **Log Level** drop-down list, select the logging level corresponding to the amount of information that you want to include in log files:

Logging Level	Description
OFF	Disables all logging.
FATAL	Logs severe error events that lead the connector to abort.
ERROR	Logs error events that might allow the connector to continue running.
WARNING	Logs events that might result in an error if action is not taken.
INFO	Logs general information that describes the progress of the connector.

Logging Level	Description
DEBUG	Logs detailed information that is useful for debugging the connector.
TRACE	Logs all connector activity.

- In the **Log Path** field, specify the full path to the folder where you want to save log files.
- If requested by Technical Support, type the name of the component for which to log messages in the **Log Namespace** field. Otherwise, do not type a value in the field.
- In the **Max Number Files** field, type the maximum number of log files to keep.

 **Note:**

After the maximum number of log files is reached, each time an additional file is created, the connector deletes the oldest log file.

- In the **Max File Size** field, type the maximum size of each log file in megabytes (MB).

 **Note:**

After the maximum file size is reached, the connector creates a new file and continues logging.

- Click **OK**.
- Restart your ODBC application to make sure that the new settings take effect.

The Simba Apache Hive ODBC Connector produces the following log files at the location you specify in the Log Path field:

- A `simbahiveodbcdriver.log` file that logs connector activity that is not specific to a connection.
- A `simbahiveodbcdriver_connection_[Number].log` file for each connection made to the database, where *[Number]* is a number that identifies each log file. This file logs connector activity that is specific to the connection.

If you enable the `UseLogPrefix` connection property, the connector prefixes the log file name with the user name associated with the connection and the process ID of the application through which the connection is made. For more information, see [UseLogPrefix](#) on page 114.

### To disable connector logging on Windows:

1. Open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Logging Options**.
2. From the **Log Level** drop-down list, select **LOG\_OFF**.
3. Click **OK**.
4. Restart your ODBC application to make sure that the new settings take effect.

## Configuring Logging for the Current Connection

You can configure logging for the current connection by setting the logging configuration properties in the DSN or in a connection string. For information about the logging configuration properties, see [Configuring Logging Options on Windows](#) on page 28. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

#### Note:

If the LogLevel configuration property is passed in via the connection string or DSN, the rest of the logging configurations are read from the connection string or DSN and not from the existing connector-wide logging configuration.

To configure logging properties in the DSN, you must modify the Windows registry. For information about the Windows registry, see the Microsoft Windows documentation.

#### Important:

Editing the Windows Registry incorrectly can potentially cause serious, system-wide problems that may require re-installing Windows to correct.

### To add logging configurations to a DSN on Windows:

1. On the Start screen, type **regedit**, and then click the **regedit** search result.
2. Navigate to the appropriate registry key for the bitness of your connector and your machine:
  - 32-bit System DSNs: HKEY\_LOCAL\_MACHINE\SOFTWARE\WOW6432Node\ODBC\ODBC.INI\*[DSN Name]*
  - 64-bit System DSNs: HKEY\_LOCAL\_MACHINE\SOFTWARE\ODBC\ODBC.INI\*[DSN Name]*
  - 32-bit and 64-bit User DSNs: HKEY\_CURRENT\_USER\SOFTWARE\ODBC\ODBC.INI\*[DSN Name]*
3. For each configuration option that you want to configure for the current connection, create a value by doing the following:

- a. If the key name value does not already exist, create it. Right-click the *[DSN Name]* and then select **New > String Value**, type the key name of the configuration option, and then press **Enter**.
  - b. Right-click the key name and then click **Modify**.  
  
To confirm the key names for each configuration option, see [Connector Configuration Options](#) on page 81.
  - c. In the Edit String dialog box, in the **Value Data** field, type the value for the configuration option.
4. Close the Registry Editor.
  5. Restart your ODBC application to make sure that the new settings take effect.

## Configuring Kerberos Authentication for Windows

### Active Directory

The Simba Apache Hive ODBC Connector supports Active Directory Kerberos on Windows. There are two prerequisites for using Active Directory Kerberos on Windows:

- MIT Kerberos is not installed on the client Windows machine.
- The MIT Kerberos Hadoop realm has been configured to trust the Active Directory realm so that users in the Active Directory realm can access services in the MIT Kerberos Hadoop realm.


### MIT Kerberos

#### Downloading and Installing MIT Kerberos for Windows 4.0.1

For information about Kerberos and download links for the installer, see the MIT Kerberos website: <http://web.mit.edu/kerberos/>.

#### To download and install MIT Kerberos for Windows 4.0.1:

1. Download the appropriate Kerberos installer:
  - For a 64-bit machine, use the following download link from the MIT Kerberos website: <http://web.mit.edu/kerberos/dist/kfw/4.0/kfw-4.0.1-amd64.msi>.
  - For a 32-bit machine, use the following download link from the MIT Kerberos website: <http://web.mit.edu/kerberos/dist/kfw/4.0/kfw-4.0.1-i386.msi>.

 **Note:**


The 64-bit installer includes both 32-bit and 64-bit libraries. The 32-bit installer includes 32-bit libraries only.

2. To run the installer, double-click the `.msi` file that you downloaded above.
3. Follow the instructions in the installer to complete the installation process.
4. When the installation completes, click **Finish**.

## Setting Up the Kerberos Configuration File

Settings for Kerberos are specified through a configuration file. You can set up the configuration file as an `.ini` file in the default location, which is the `C:\ProgramData\MIT\Kerberos5` directory, or as a `.conf` file in a custom location.

Normally, the `C:\ProgramData\MIT\Kerberos5` directory is hidden. For information about viewing and using this hidden directory, refer to Microsoft Windows documentation.


 **Note:**

For more information on configuring Kerberos, refer to the MIT Kerberos documentation.

### To set up the Kerberos configuration file in the default location:

1. Obtain a `krb5.conf` configuration file. You can obtain this file from your Kerberos administrator, or from the `/etc/krb5.conf` folder on the machine that is hosting the Hive Server 2 instance.
2. Rename the configuration file from `krb5.conf` to `krb5.ini`.
3. Copy the `krb5.ini` file to the `C:\ProgramData\MIT\Kerberos5` directory and overwrite the empty sample file.

### To set up the Kerberos configuration file in a custom location:

1. Obtain a `krb5.conf` configuration file. You can obtain this file from your Kerberos administrator, or from the `/etc/krb5.conf` folder on the machine that is hosting the Hive Server 2 instance.
2. Place the `krb5.conf` file in an accessible directory and make note of the full path name.
3. Open the System window:
  - If you are using Windows 7 or earlier, click **Start** , then right-click **Computer**, and then click **Properties**.




- Or, if you are using Windows 8 or later, right-click **This PC** on the Start screen, and then click **Properties**.
4. Click **Advanced System Settings**.
  5. In the System Properties dialog box, click the **Advanced** tab and then click **Environment Variables**.
  6. In the Environment Variables dialog box, under the System Variables list, click **New**.
  7. In the New System Variable dialog box, in the **Variable Name** field, type **KRB5\_CONFIG**.
  8. In the **Variable Value** field, type the full path to the `krb5.conf` file.
  9. Click **OK** to save the new variable.
  10. Make sure that the variable is listed in the System Variables list.
  11. Click **OK** to close the Environment Variables dialog box, and then click **OK** to close the System Properties dialog box.

## Setting Up the Kerberos Credential Cache File

Kerberos uses a credential cache to store and manage credentials.

### To set up the Kerberos credential cache file:

1. Create a directory where you want to save the Kerberos credential cache file. For example, create a directory named `C:\temp`.
2. Open the System window:
  - If you are using Windows 7 or earlier, click **Start** , then right-click **Computer**, and then click **Properties**.
  - Or, if you are using Windows 8 or later, right-click **This PC** on the Start screen, and then click **Properties**.
3. Click **Advanced System Settings**.
4. In the System Properties dialog box, click the **Advanced** tab and then click **Environment Variables**.
5. In the Environment Variables dialog box, under the System Variables list, click **New**.
6. In the New System Variable dialog box, in the **Variable Name** field, type **KRB5CCNAME**.
7. In the **Variable Value** field, type the path to the folder you created above, and then append the file name `krb5cache`. For example, if you created the folder `C:\temp`, then type `C:\temp\krb5cache`.

 **Note:**

`krb5cache` is a file (not a directory) that is managed by the Kerberos software, and it should not be created by the user. If you receive a permission error when you first use Kerberos, make sure that the `krb5cache` file does not already exist as a file or a directory.

8. Click **OK** to save the new variable.
9. Make sure that the variable appears in the System Variables list.
10. Click **OK** to close the Environment Variables dialog box, and then click **OK** to close the System Properties dialog box.
11. To make sure that Kerberos uses the new settings, restart your machine.

## Obtaining a Ticket for a Kerberos Principal


A principal refers to a user or service that can authenticate to Kerberos. To authenticate to Kerberos, a principal must obtain a ticket by using a password or a keytab file. You can specify a keytab file to use, or use the default keytab file of your Kerberos configuration.

### To obtain a ticket for a Kerberos principal using a password:

1. Open MIT Kerberos Ticket Manager.
2. In MIT Kerberos Ticket Manager, click **Get Ticket**.
3. In the Get Ticket dialog box, type your principal name and password, and then click **OK**.

If the authentication succeeds, then your ticket information appears in MIT Kerberos Ticket Manager.

### To obtain a ticket for a Kerberos principal using a keytab file:

1. Open a command prompt:
  - If you are using Windows 7 or earlier, click **Start** , then click **All Programs**, then click **Accessories**, and then click **Command Prompt**.
  - If you are using Windows 8 or later, click the arrow button at the bottom of the Start screen, then find the Windows System program group, and then click **Command Prompt**.
2. In the Command Prompt, type a command using the following syntax:

```
kinit -k -t [KeytabPath][Principal]
```

*[KeytabPath]* is the full path to the keytab file. For example:

```
C:\mykeytabs\myUser.keytab.
```

*[Principal]* is the Kerberos user principal to use for authentication. For example:  
myUser@EXAMPLE.COM.

3. If the cache location KRB5CCNAME is not set or used, then use the `-c` option of the `kinit` command to specify the location of the credential cache. In the command, the `-c` argument must appear last. For example:


```
kinit -k -t C:\mykeytabs\myUser.keytab
myUser@EXAMPLE.COM -c C:\ProgramData\MIT\krbcache
```

Krbcache is the Kerberos cache file, not a directory.

### To obtain a ticket for a Kerberos principal using the default keytab file:

#### Note:

For information about configuring a default keytab file for your Kerberos configuration, refer to the MIT Kerberos documentation.

1. Open a command prompt:
  - If you are using Windows 7 or earlier, click **Start** , then click **All Programs**, then click **Accessories**, and then click **Command Prompt**.
  - If you are using Windows 8 or later, click the arrow button at the bottom of the Start screen, then find the Windows System program group, and then click **Command Prompt**.
2. In the Command Prompt, type a command using the following syntax:

```
kinit -k [principal]
```

*[principal]* is the Kerberos user principal to use for authentication. For example:  
MyUser@EXAMPLE.COM.

3. If the cache location KRB5CCNAME is not set or used, then use the `-c` option of the `kinit` command to specify the location of the credential cache. In the command, the `-c` argument must appear last. For example:

```
kinit -k -t C:\mykeytabs\myUser.keytab
myUser@EXAMPLE.COM -c C:\ProgramData\MIT\krbcache
```

Krbcache is the Kerberos cache file, not a directory.


## Verifying the Connector Version Number on Windows

If you need to verify the version of the Simba Apache Hive ODBC Connector that is installed on your Windows machine, you can find the version number in the ODBC

Data Source Administrator.

**To verify the connector version number on Windows:**

1. From the Start menu, go to **ODBC Data Sources**.

 **Note:**

Make sure to select the ODBC Data Source Administrator that has the same bitness as the client application that you are using to connect to Hive.

2. Click the **Drivers** tab and then find the Simba Apache Hive ODBC Connector in the list of ODBC connectors that are installed on your system. The version number is displayed in the **Version** column.

## macOS Connector

### macOS System Requirements

The Simba Apache Hive ODBC Connector supports Apache Hive versions 1.0.0 through 3.1.0.

Install the connector on client machines where the application is installed. Each client machine that you install the connector on must meet the following minimum system requirements:

- macOS version 10.13 or 10.14
- 100MB of available disk space
- One of the following ODBC driver managers installed:
  - iODBC 3.52.9 or later
  - unixODBC 2.2.14 or later

### Installing the Connector on macOS

If you did not obtain this connector from the Simba website, you might need to follow a different installation procedure. For more information, see the *Simba OEM ODBC Connectors Installation Guide*.

The Simba Apache Hive ODBC Connector is available for macOS as a .dmg file named `SimbaHiveODBC.dmg`. The connector supports both 32- and 64-bit client applications.

**To install the Simba Apache Hive ODBC Connector on macOS:**

1. Double-click **SimbaHiveODBC.dmg** to mount the disk image.
2. Double-click **SimbaHiveODBC.pkg** to run the installer.
3. In the installer, click **Continue**.
4. On the Software License Agreement screen, click **Continue**, and when the prompt appears, click **Agree** if you agree to the terms of the License Agreement.
5. Optionally, to change the installation location, click **Change Install Location**, then select the desired location, and then click **Continue**.

 **Note:**

By default, the connector files are installed in the `/Library/simba/hive` directory.

6. To accept the installation location and begin the installation, click **Install**.
7. When the installation completes, click **Close**.
8. If you received a license file through email, then copy the license file into the `/lib` subfolder in the connector installation directory. You must have root privileges when changing the contents of this folder.

For example, if you installed the connector to the default location, you would copy the license file into the `/Library/simba/hive/lib` folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the connector. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 48.

## Verifying the Connector Version Number on macOS

If you need to verify the version of the Simba Apache Hive ODBC Connector that is installed on your macOS machine, you can query the version number through the Terminal.

**To verify the connector version number on macOS:**

- At the Terminal, run the following command:

```
pkgutil --info simba.hiveodbc
```

The command returns information about the Simba Apache Hive ODBC Connector that is installed on your machine, including the version number.

# Linux Connector

For most Linux distributions, you can install the connector using the RPM file or the tarball package. If you are installing the connector on a Debian machine, you must use the Debian package.

## Linux System Requirements

The Simba Apache Hive ODBC Connector supports Apache Hive versions 1.0.0 through 3.1.0.

Install the connector on client machines where the application is installed. Each client machine that you install the connector on must meet the following minimum system requirements:

- One of the following distributions:
  - Red Hat® Enterprise Linux® (RHEL) 7
  - CentOS 7
  - SUSE Linux Enterprise Server (SLES) 11 or 12
  - Debian 8 or 9
  - Ubuntu 14.04, 16.04, or 18.04
  - Oracle Linux 7.5 or 7.6
- 150 MB of available disk space
- One of the following ODBC driver managers installed:
  - iODBC 3.52.9 or later
  - unixODBC 2.2.14 or later
- All of the following `libsasl` libraries installed:
  - `cyrus-sasl-2.1.22-7` or later
  - `cyrus-sasl-gssapi-2.1.22-7` or later
  - `cyrus-sasl-plain-2.1.22-7` or later

 **Note:**

If the package manager in your Linux distribution cannot resolve the dependencies automatically when installing the connector, then download and manually install the packages.

To install the connector, you must have root access on the machine.

## Installing the Connector Using the RPM File

If you did not obtain this connector from the Simba website, you might need to follow a different installation procedure. For more information, see the *Simba OEM ODBC Connectors Installation Guide*.

On 64-bit editions of Linux, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit connectors, and 32-bit applications must use 32-bit connectors. Make sure that you use a connector whose bitness matches the bitness of the client application:

- `SimbaHiveODBC-32bit-[Version]-[Release].i686.rpm` for the 32-bit connector
- `SimbaHiveODBC-[Version]-[Release].x86_64.rpm` for the 64-bit connector

The placeholders in the file names are defined as follows:

- `[Version]` is the version number of the connector.
- `[Release]` is the release number for this version of the connector.

You can install both the 32-bit and 64-bit versions of the connector on the same machine.

### To install the Simba Apache Hive ODBC Connector using the RPM File:

1. Log in as the root user.
2. Navigate to the folder containing the RPM package for the connector.
3. Depending on the Linux distribution that you are using, run one of the following commands from the command line, where `[RPMFileName]` is the file name of the RPM package:
  - If you are using Red Hat Enterprise Linux or CentOS, run the following command:


```
yum --nogpgcheck localinstall [RPMFileName]
```

- Or, if you are using SUSE Linux Enterprise Server, run the following command:

```
zypper install [RPMFileName]
```

The Simba Apache Hive ODBC Connector files are installed in the `/opt/simba/hive` directory.



 **Note:**

If the package manager in your Linux distribution cannot resolve the `libsasl` dependencies automatically when installing the connector, then download and manually install the packages.

4. If you received a license file through email, then copy the license file into the `/opt/simba/hive/lib/32` or `/opt/simba/hive/lib/64` folder, depending on the version of the connector that you installed.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the connector. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 48.

## Installing the Connector Using the Tarball Package

If you did not obtain this connector from the Simba website, you might need to follow a different installation procedure. For more information, see the *Simba OEM ODBC Connectors Installation Guide*.

The Simba Apache Hive ODBC Connector is available as a tarball package named `SimbaHiveODBC-[Version].[Release]-Linux.tar.gz`, where *[Version]* is the version number of the connector and *[Release]* is the release number for this version of the connector. The package contains both the 32-bit and 64-bit versions of the connector.

On 64-bit editions of Linux, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit connectors, and 32-bit applications must use 32-bit connectors. Make sure that you use a connector whose bitness matches the bitness of the client application. You can install both versions of the connector on the same machine.

### To install the connector using the tarball package:

1. Log in as the root user, and then navigate to the folder containing the tarball package.
2. Run the following command to extract the package and install the connector:

```
tar --directory=/opt -zxvf [TarballName]
```

Where *[TarballName]* is the name of the tarball package containing the connector.

The Simba Apache Hive ODBC Connector files are installed in the `opt/simba/hive` directory.

3. If you received a license file through email, then copy the license file into the `opt/simba/hive/lib/32` or `opt/simba/hive/lib/64` folder, depending on the version of the connector that you installed.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the connector. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 48.

## Installing the Connector on Debian

To install the connector on a Debian machine, use the Debian package instead of the RPM file or tarball package.

On 64-bit editions of Debian, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit connectors, and 32-bit applications must use 32-bit connectors. Make sure that you use the version of the connector that matches the bitness of the client application:

- `simbahive_[Version]-[Release]_i386.deb` for the 32-bit connector
- `simbahive_[Version]-[Release]_amd64.deb` for the 64-bit connector

`[Version]` is the version number of the connector, and `[Release]` is the release number for this version of the connector.

You can install both versions of the connector on the same machine.

### To install the Simba Apache Hive ODBC Connector on Debian:

1. Log in as the root user, and then navigate to the folder containing the Debian package for the connector.
2. Double-click `simbahive_[Version]-[Release]_i386.deb` or `simbahive_[Version]-[Release]_amd64.deb`.
3. Follow the instructions in the installer to complete the installation process.

The Simba Apache Hive ODBC Connector files are installed in the `/opt/simba/hive` directory.

#### Note:

If the package manager in your Ubuntu distribution cannot resolve the `libsasl` dependencies automatically when installing the connector, then download and manually install the packages required by the version of the connector that you want to install.

4. If you received a license file via email, then copy the license file into the `/opt/simba/hive/lib/32` or `/opt/simba/hiveodbc/lib/64` folder,

depending on the version of the connector that you installed. You must have root privileges when changing the contents of this folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the connector. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 48.

## Verifying the Connector Version Number on Linux

If you need to verify the version of the Simba Apache Hive ODBC Connector that is installed on your Linux machine, you can query the version number through the command-line interface if the connector was installed using an RPM file or Debian package. Alternatively, you can search the connector's binary file for version number information.

**To verify the connector version number on Linux using the command-line interface:**

- Depending on your package manager, at the command prompt, run one of the following commands:

- ```
yum list | grep SimbaHiveODBC
```

- ```
rpm -qa | grep SimbaHiveODBC
```

- ```
dpkg -l | grep simbahiveodbc
```

The command returns information about the Simba Apache Hive ODBC Connector that is installed on your machine, including the version number.

**To verify the connector version number on Linux using the binary file:**

1. Navigate to the `/lib` subfolder in your connector installation directory. By default, the path to this directory is: `/opt/simba/hive/lib`.
2. Open the connector's `.so` binary file in a text editor, and search for the text `$driver_version_sb$:`. The connector's version number is listed after this text.

# AIX Connector

## AIX System Requirements

The Simba Apache Hive ODBC Connector supports Apache Hive versions 1.0.0 through 3.1.0.

Install the connector on client machines where the application is installed. Each machine that you install the connector on must meet the following minimum system requirements:

- IBM AIX 5.3, 6.1, or 7.1
- 150 MB of available disk space
- One of the following ODBC driver managers installed:
  - iODBC 3.52.9 or later
  - unixODBC 2.2.14 or later

To install the connector, you must have root access on the machine.

## Installing the Connector on AIX

On 64-bit editions of AIX, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit connectors, and 32-bit applications must use 32-bit connectors. Make sure that you use the version of the connector that matches the bitness of the client application:

- `SimbaHiveODBC-32bit-[Version]-[Release].ppc.rpm` for the 32-bit connector
- `SimbaHiveODBC-[Version]-[Release].ppc.rpm` for the 64-bit connector

*[Version]* is the version number of the connector, and *[Release]* is the release number for this version of the connector.

You can install both versions of the connector on the same machine.

### To install the Simba Apache Hive ODBC Connector on AIX:

1. Log in as the root user, and then navigate to the folder containing the RPM package for the connector.
2. Run the following command from the command line, where *[RPMFileName]* is the file name of the RPM package:

```
rpm --install [RPMFileName]
```

The Simba Apache Hive ODBC Connector files are installed in the `/opt/simba/hive` directory.

3. If you received a license file via email, then copy the license file into the `/opt/simba/hive/lib/32` or `/opt/simba/hive/lib/64` folder, depending on the version of the connector that you installed. You must have root privileges when changing the contents of this folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the connector. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 48.

## Verifying the Connector Version Number on AIX

If you need to verify the version of the Simba Apache Hive ODBC Connector that is installed on your AIX machine, you can query the version number through the command-line interface.

**To verify the connector version number on AIX:**

- At the command prompt, run the following command:

```
rpm -qa | grep SimbaHiveODBC
```

The command returns information about the Simba Apache Hive ODBC Connector that is installed on your machine, including the version number.

# Solaris Connector

## Solaris System Requirements

The Simba Apache Hive ODBC Connector supports Apache Hive versions 1.0.0 through 3.1.0.

Install the connector on client machines where the application is installed. Each machine that you install the connector on must meet the following minimum system requirements:

- Solaris 10 or 11 (SPARC and SPARC64 editions only)
- 150 MB of available disk space
- One of the following ODBC driver managers installed:
  - iODBC 3.52.9 or later
  - unixODBC 2.2.14 or later

To install the connector, you must have root access on the machine.

## Installing the Connector on Solaris

The Simba Apache Hive ODBC Connector is available for Solaris as a tarball package named `Simba Apache Hive ODBC Connector_Solaris_gcc_[Version].[Release]_Solaris.tar.gz`, where *[Version]* is the version number of the connector and *[Release]* is the release number for this version of the connector. The package contains both the 32-bit and 64-bit versions of the connector.

On sparc64 editions of Solaris, you can execute both sparc and sparc64 applications. However, sparc64 applications must use 64-bit connectors, and sparc applications must use 32-bit connectors. Make sure that you use the version of the connector that matches the bitness of the client application. You can install both versions of the connector on the same machine.

**To install the Simba Apache Hive ODBC Connector on Solaris:**

1. Log in as the root user, and then navigate to the folder containing the tarball package.
2. Run the following command to extract the package and install the connector:

```
tar --directory=/opt -zxvf [TarballName]
```

Where *[TarballName]* is the name of the tarball package containing the connector.

The Simba Apache Hive ODBC Connector files are installed in the `/opt/simba/hive/` directory.

3. If you received a license file via email, then copy the license file into the `/opt/simba/hive/lib/32` or `/opt/simba/hive/lib/64` folder, depending on the version of the connector that you installed. You must have root privileges when changing the contents of this folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the connector. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 48.

## Verifying the Connector Version Number on Solaris

If you need to verify the version of the Simba Apache Hive ODBC Connector that is installed on your Solaris machine, you can query the version number through the command-line interface.

**To verify the connector version number on Solaris:**

- At the command prompt, run the following command:

```
rpm -qa | grep SimbaHiveODBC
```

The command returns information about the Simba Apache Hive ODBC Connector that is installed on your machine, including the version number.

## Configuring the ODBC Driver Manager on Non-Windows Machines

To make sure that the ODBC driver manager on your machine is configured to work with the Simba Apache Hive ODBC Connector, do the following:

- Set the library path environment variable to make sure that your machine uses the correct ODBC driver manager. For more information, see [Specifying ODBC Driver Managers on Non-Windows Machines](#) on page 48.
- If the connector configuration files are not stored in the default locations expected by the ODBC driver manager, then set environment variables to make sure that the driver manager locates and uses those files. For more information, see [Specifying the Locations of the Connector Configuration Files](#) on page 49.

After configuring the ODBC driver manager, you can configure a connection and access your data store through the connector.

## Specifying ODBC Driver Managers on Non-Windows Machines

You need to make sure that your machine uses the correct ODBC driver manager to load the connector. To do this, set the library path environment variable.

### macOS

If you are using a macOS machine, then set the `DYLD_LIBRARY_PATH` environment variable to include the paths to the ODBC driver manager libraries. For example, if the libraries are installed in `/usr/local/lib`, then run the following command to set `DYLD_LIBRARY_PATH` for the current user session:

```
export DYLD_LIBRARY_PATH=$DYLD_LIBRARY_PATH:/usr/local/lib
```

For information about setting an environment variable permanently, refer to the macOS shell documentation.

### Linux or AIX

If you are using a Linux or AIX machine, then set the `LD_LIBRARY_PATH` environment variable to include the paths to the ODBC driver manager libraries. For example, if the libraries are installed in `/usr/local/lib`, then run the following command to set `LD_LIBRARY_PATH` for the current user session:



```
export LD_LIBRARY_PATH=$LD_LIBRARY_PATH:/usr/local/lib
```

For information about setting an environment variable permanently, refer to the Linux or AIX shell documentation.

## Solaris

If you are using a Solaris machine, then set the `LD_LIBRARY_PATH` environment variable to include the paths to the ODBC driver manager libraries and the third-party libraries that are installed with the driver. For example, if the driver manager libraries are installed in `/usr/local/lib` and the 32-bit driver is installed in `/opt/simba/hive`, then run the following command to set `LD_LIBRARY_PATH` for the current user session:

```
export LD_LIBRARY_PATH=$LD_LIBRARY_
PATH:/usr/local/lib:/opt/simba/hive/lib/32
```

For information about setting an environment variable permanently, refer to the Solaris shell documentation.

## Specifying the Locations of the Connector Configuration Files

By default, ODBC driver managers are configured to use hidden versions of the `odbc.ini` and `odbcinst.ini` configuration files (named `.odbc.ini` and `.odbcinst.ini`) located in the home directory, as well as the `simba.hiveodbc.ini` file in the `lib` subfolder of the connector installation directory. If you store these configuration files elsewhere, then you must set the environment variables described below so that the driver manager can locate the files.

If you are using iODBC, do the following:

- Set `ODBCINI` to the full path and file name of the `odbc.ini` file.
- Set `ODBCINSTINI` to the full path and file name of the `odbcinst.ini` file.
- Set `SIMBAHIVEINI` to the full path and file name of the `simba.hiveodbc.ini` file.

If you are using unixODBC, do the following:

- Set `ODBCINI` to the full path and file name of the `odbc.ini` file.
- Set `ODBCSYSINI` to the full path of the directory that contains the `odbcinst.ini` file.

- Set `SIMBAHIVEINI` to the full path and file name of the `simba.hiveodbc.ini` file.

For example, if your `odbc.ini` and `odbcinst.ini` files are located in `/usr/local/odbc` and your `simba.hiveodbc.ini` file is located in `/etc`, then set the environment variables as follows:

For iODBC:

```
export ODBCINI=/usr/local/odbc/odbc.ini
export ODBCINSTINI=/usr/local/odbc/odbcinst.ini
export SIMBAHIVEINI=/etc/simba.hiveodbc.ini
```

For unixODBC:

```
export ODBCINI=/usr/local/odbc/odbc.ini
export ODBCYSINI=/usr/local/odbc
export SIMBAHIVEINI=/etc/simba.hiveodbc.ini
```

To locate the `simba.hiveodbc.ini` file, the connector uses the following search order:

1. If the `SIMBAHIVEINI` environment variable is defined, then the connector searches for the file specified by the environment variable.
2. The connector searches the directory that contains the connector library files for a file named `simba.hiveodbc.ini`.
3. The connector searches the current working directory of the application for a file named `simba.hiveodbc.ini`.
4. The connector searches the home directory for a hidden file named `.simba.hiveodbc.ini` (prefixed with a period).
5. The connector searches the `/etc` directory for a file named `simba.hiveodbc.ini`.

## Configuring ODBC Connections on a Non-Windows Machine

The following sections describe how to configure ODBC connections when using the Simba Apache Hive ODBC Connector on non-Windows platforms:

- [Creating a Data Source Name on a Non-Windows Machine](#) on page 51
- [Configuring a DSN-less Connection on a Non-Windows Machine](#) on page 55
- [Configuring Service Discovery Mode on a Non-Windows Machine](#) on page 57
- [Configuring Authentication on a Non-Windows Machine](#) on page 58
- [Configuring SSL Verification on a Non-Windows Machine](#) on page 62
- [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 63
- [Configuring Logging Options on a Non-Windows Machine](#) on page 64
- [Setting Connector-Wide Configuration Options on a Non-Windows Machine](#) on page 66
- [Testing the Connection on a Non-Windows Machine](#) on page 67

### Creating a Data Source Name on a Non-Windows Machine

Typically, after installing the Simba Apache Hive ODBC Connector, you need to create a Data Source Name (DSN). A DSN is a data structure that stores connection information so that it can be used by the connector to connect to Hive.

You can specify connection settings in a DSN (in the `odbc.ini` file), in a connection string, or as connector-wide settings (in the `simba.hiveodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

The following instructions describe how to create a DSN by specifying connection settings in the `odbc.ini` file. If your machine is already configured to use an existing `odbc.ini` file, then update that file by adding the settings described below. Otherwise, copy the `odbc.ini` file from the `Setup` subfolder in the connector installation directory to the home directory, and then update the file as described below.

For information about specifying settings in a connection string, see [Configuring a DSN-less Connection on a Non-Windows Machine](#) on page 55 and [Using a Connection String](#) on page 71. For information about connector-wide settings, see [Setting Connector-Wide Configuration Options on a Non-Windows Machine](#) on page 66.

**To create a Data Source Name on a non-Windows machine:**

1. In a text editor, open the `odbc.ini` configuration file.

**Note:**

If you are using a hidden copy of the `odbc.ini` file, you can remove the period (.) from the start of the file name to make the file visible while you are editing it.

2. In the `[ODBC Data Sources]` section, add a new entry by typing a name for the DSN, an equal sign (=), and then the name of the connector.

For example, on a macOS machine:

```
[ODBC Data Sources]
Sample DSN=Simba Apache Hive ODBC Connector
```

As another example, for a 32-bit connector on a Linux/AIX/Solaris/Debian machine:

```
[ODBC Data Sources]
Sample DSN=Simba Apache Hive ODBC Connector 32-bit
```

3. Create a section that has the same name as your DSN, and then specify configuration options as key-value pairs in the section:
  - a. Set the `Driver` property to the full path of the connector library file that matches the bitness of the application.

For example, on a macOS machine:

```
Driver=/Library/simba/hive/lib/libhiveodbc_sbu.dylib
```

As another example, for a 32-bit connector on a Linux/AIX/Solaris/Debian machine:

```
Driver=/opt/simba/hive/lib/32/libhiveodbc_sb32.so
```

- b. Set the `HiveServerType` property to one of the following values:
  - If you are running Hive Server 1, set the property to 1.
  - If you are running Hive Server 2, set the property to 2.

For example:


```
HiveServerType=1
```

- c. Specify whether the connector uses the ZooKeeper service when connecting to Hive, and provide the necessary connection information:

- To connect to Hive without using the ZooKeeper service do the following:
  - a. Set the `ServiceDiscoveryMode` property to 0.
  - b. Set the `Host` property to the IP address or host name of the server.
  - c. Set the `Port` property to the number of the TCP port that the server uses to listen for client connections

For example:

```
ServiceDiscoveryMode=0
Host=192.168.222.160
Port=10000
```

- Or, to discover Hive Server 2 services through the ZooKeeper service, set properties as described in [Configuring Service Discovery Mode on a Non-Windows Machine](#) on page 57.
  - d. If authentication is required to access the server, then specify the authentication mechanism and your credentials. For more information, see [Configuring Authentication on a Non-Windows Machine](#) on page 58.
  - e. If you want to connect to the server through SSL, then enable SSL and specify the certificate information. For more information, see [Configuring SSL Verification on a Non-Windows Machine](#) on page 62.
-  **Note:**  
If the `AuthMech` property is set to 2, SSL is not available.
- f. If you want to configure server-side properties, then set them as key-value pairs using a special syntax. For more information, see [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 63.
  - g. Optionally, set additional key-value pairs as needed to specify other optional connection settings. For detailed information about all the configuration options supported by the Simba Apache Hive ODBC Connector, see [Connector Configuration Options](#) on page 81.
4. Save the `odbc.ini` configuration file.

 **Note:**

If you are storing this file in its default location in the home directory, then prefix the file name with a period (.) so that the file becomes hidden. If you are storing this file in another location, then save it as a non-hidden file (without the prefix), and make sure that the ODBCINI environment variable specifies the location. For more information, see [Specifying the Locations of the Connector Configuration Files](#) on page 49.

For example, the following is an `odbc.ini` configuration file for macOS containing a DSN that connects to a Hive Thrift Server instance directly and authenticates the connection using a user name and password:

```
[ODBC Data Sources]
Sample DSN=Simba Apache Hive ODBC Connector
[Sample DSN]
Driver=/Library/simba/hive/lib/libhiveodbc_sbu.dylib
HiveServerType=2
ServiceDiscoveryMode=0
Host=192.168.222.160
Port=10000
UID=username
PWD=userpassword
```

As another example, the following is an `odbc.ini` configuration file for a 32-bit connector on a Linux/AIX/Solaris/Debian machine, containing a DSN that connects to a Hive Thrift Server instance directly and authenticates the connection using a user name and password:

```
[ODBC Data Sources]
Sample DSN=Simba Apache Hive ODBC Connector 32-bit
[Sample DSN]
Driver=/opt/simba/hive/lib/32/libhiveodbc_sb32.so
HiveServerType=2
ServiceDiscoveryMode=0
Host=192.168.222.160
Port=10000
UID=username
PWD=userpassword
```

You can now use the DSN in an application to connect to the data store.


## Configuring a DSN-less Connection on a Non-Windows Machine

To connect to your data store through a DSN-less connection, you need to define the connector in the `odbcinst.ini` file and then provide a DSN-less connection string in your application.

If your machine is already configured to use an existing `odbcinst.ini` file, then update that file by adding the settings described below. Otherwise, copy the `odbcinst.ini` file from the `Setup` subfolder in the connector installation directory to the home directory, and then update the file as described below.

**To define a connector on a non-Windows machine:**

1. In a text editor, open the `odbcinst.ini` configuration file.

 **Note:**

If you are using a hidden copy of the `odbcinst.ini` file, you can remove the period (.) from the start of the file name to make the file visible while you are editing it.

2. In the `[ODBC Drivers]` section, add a new entry by typing a name for the connector, an equal sign (=), and then `Installed`.

For example:

```
[ODBC Drivers]
Simba Apache Hive ODBC Connector=Installed
```

3. Create a section that has the same name as the connector (as specified in the previous step), and then specify the following configuration options as key-value pairs in the section:
  - a. Set the `Driver` property to the full path of the connector library file that matches the bitness of the application.

For example, on a macOS machine:

```
Driver=/Library/simba/hive/lib/libhiveodbc_sbu.dylib
```

As another example, for a 32-bit connector on a Linux/AIX/Solaris/Debian machine:

```
Driver=/opt/simba/hive/lib/32/libhiveodbc_sb32.so
```

- b. Optionally, set the `Description` property to a description of the connector.

For example:

```
Description=Simba Apache Hive ODBC Connector
```

4. Save the `odbcinst.ini` configuration file.

 **Note:**

If you are storing this file in its default location in the home directory, then prefix the file name with a period (.) so that the file becomes hidden. If you are storing this file in another location, then save it as a non-hidden file (without the prefix), and make sure that the `ODBCINSTINI` or `ODBCSYSINI` environment variable specifies the location. For more information, see [Specifying the Locations of the Connector Configuration Files](#) on page 49.

For example, the following is an `odbcinst.ini` configuration file for macOS:

```
[ODBC Drivers]
Simba Apache Hive ODBC Connector=Installed
[Simba Apache Hive ODBC Connector]
Description=Simba Apache Hive ODBC Connector
Driver=/Library/simba/hive/lib/libhiveodbc_sbu.dylib
```

As another example, the following is an `odbcinst.ini` configuration file for both the 32- and 64-bit connectors on Linux/AIX/Solaris/Debian:

```
[ODBC Drivers]
Simba Apache Hive ODBC Connector 32-bit=Installed
Simba Apache Hive ODBC Connector 64-bit=Installed
[Simba Apache Hive ODBC Connector 32-bit]
Description=Simba Apache Hive ODBC Connector (32-bit)
Driver=/opt/simba/hive/lib/32/libhiveodbc_sb32.so
[Simba Apache Hive ODBC Connector 64-bit]
Description=Simba Apache Hive ODBC Connector (64-bit)
Driver=/opt/simba/hive/lib/64/libhiveodbc_sb64.so
```

You can now connect to your data store by providing your application with a connection string where the `Driver` property is set to the connector name specified in the `odbcinst.ini` file, and all the other necessary connection properties are also set. For more information, see "DSN-less Connection String Examples" in [Using a Connection String](#) on page 71.

For instructions about configuring specific connection features, see the following:



- [Configuring Service Discovery Mode on a Non-Windows Machine](#) on page 57
- [Configuring Authentication on a Non-Windows Machine](#) on page 58
- [Configuring SSL Verification on a Non-Windows Machine](#) on page 62
- [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 63

For detailed information about all the connection properties that the connector supports, see [Connector Configuration Options](#) on page 81.

## Configuring Service Discovery Mode on a Non-Windows Machine

You can configure the Simba Apache Hive ODBC Connector to discover Hive Server 2 services through ZooKeeper.

You can set the connection properties described below in a connection string, in a DSN (in the `odbc.ini` file), or as a connector-wide setting (in the `simba.hiveodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

### To enable Service Discovery Mode on a non-Windows machine:

1. Set the `ServiceDiscoveryMode` connection attribute to 1.
2. Set the `ZKNamespace` connection attribute to specify the namespace on ZooKeeper under which Hive Server 2 znodes are added.
3. Set the `Host` connection attribute to specify the ZooKeeper ensemble as a comma-separated list of ZooKeeper servers. For example, type the following, where `[ZK_Host]` is the IP address or host name of the ZooKeeper server and `[ZK_Port]` is the number of the TCP port that the ZooKeeper server uses to listen for client connections:

```
[ZK_Host1]:[ZK_Port1],[ZK_Host2]:[ZK_Port2]
```

#### ! Important:

When `ServiceDiscoveryMode` is set to 1, connections to Hive Server 1 are not supported and the `Port` connection attribute is not applicable.

## Configuring Authentication on a Non-Windows Machine

Some Hive Server 2 instances are configured to require authentication for access. To connect to a Hive server, you must configure the Simba Apache Hive ODBC Connector to use the authentication mechanism that matches the access requirements of the server and provides the necessary credentials.

For information about how to determine the type of authentication your Hive server requires, see [Authentication Mechanisms](#) on page 69.

You can set the connection properties for authentication in a connection string, in a DSN (in the `odbc.ini` file), or as a connector-wide setting (in the `simba.hiveodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

Depending on the authentication mechanism you use, there might be additional connection attributes that you must define. For more information about the attributes involved in configuring authentication, see [Connector Configuration Options](#) on page 81.

If cookie-based authentication is enabled in your Hive Server 2 database, you can specify a list of authentication cookies in the `HTTPAuthCookies` connection property. In this case, the connector authenticates the connection once based on the provided authentication credentials. It then uses the cookie generated by the server for each subsequent request in the same connection. For more information, see [HTTPAuthCookies](#) on page 112.

### Using No Authentication

When connecting to a Hive server of type Hive Server 1, you must use No Authentication. When you use No Authentication, Binary is the only Thrift transport protocol that is supported.

**To configure a connection without authentication:**

1. Set the `AuthMech` connection attribute to 0.
2. If the Hive server is configured to use SSL, then configure SSL for the connection. For more information, see [Configuring SSL Verification on a Non-Windows Machine](#) on page 62.

## Using Kerberos

Kerberos must be installed and configured before you can use this authentication mechanism. For more information, refer to the MIT Kerberos Documentation: <http://web.mit.edu/kerberos/krb5-latest/doc/>.

This authentication mechanism is available only for Hive Server 2 on non-HDInsight distributions. When you use Kerberos authentication, the Binary transport protocol is not supported.

### To configure Kerberos authentication:

1. Set the `AuthMech` connection attribute to 1.
2. Choose one:
  - To use the default realm defined in your Kerberos setup, do not set the `KrbRealm` attribute.
  - Or, if your Kerberos setup does not define a default realm or if the realm of your Hive server is not the default, then set the appropriate realm using the `KrbRealm` attribute.
3. Optionally, if you are using MIT Kerberos and a Kerberos realm is specified using the `KrbRealm` connection attribute, then choose one:
  - To have the Kerberos layer canonicalize the server's service principal name, leave the `ServicePrincipalCanonicalization` attribute set to 1.
  - Or, to prevent the Kerberos layer from canonicalizing the server's service principal name, set the `ServicePrincipalCanonicalization` attribute to 0.
4. Set the `KrbHostFQDN` attribute to the fully qualified domain name of the Hive Server 2 host.

 **Note:**

To use the Hive server host name as the fully qualified domain name for Kerberos authentication, set `KrbHostFQDN` to `_HOST`.

5. Set the `KrbServiceName` attribute to the service name of the Hive .
6. To allow the connector to pass your credentials directly to the server for use in authentication, set `DelegateKrbCreds` to 1.
7. Set the `ThriftTransport` connection attribute to the transport protocol to use in the Thrift layer.

**! Important:**

When using this authentication mechanism, Binary (`ThriftTransport=0`) is not supported.

8. If the Hive server is configured to use SSL, then configure SSL for the connection. For more information, see [Configuring SSL Verification on a Non-Windows Machine](#) on page 62.

## Using SAML 2.0


This authentication mechanism enables you to authenticate via Single Sign-On using SAML 2.0 against supported servers.

**! Important:**

In order to use SAML 2.0 for authentication, the `ThriftTransport` attribute must be set to 2 and the `SSL` attribute must be set to 1.

### To configure SAML 2.0 authentication:

1. Set the `AuthMech` connection attribute to 12.
2. Set the `ThriftTransport` attribute to 2.
3. Set the `HttpPath` attribute to the partial URL corresponding to the Hive server.
4. Set the `SSL` attribute to 1.
5. Optionally, set the `SSOIgnoreDriverNoPrompt` attribute to `true`. When the application is making a `SQLDriverConnect` call with a `SQL_DRIVER_NOPROMPT` flag, this property displays the web browser used to complete the browser based authentication flow.
6. Optionally, set the `TSaslTransportBufSize` attribute to the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

## Using User Name

This authentication mechanism requires a user name but does not require a password. The user name labels the session, facilitating database tracking.

This authentication mechanism is available only for Hive Server 2 on non-HDInsight distributions. Most default configurations of Hive Server 2 require User Name authentication. When you use User Name authentication, SSL is not supported and SASL is the only Thrift transport protocol available.

**To configure User Name authentication:**

1. Set the `AuthMech` connection attribute to 2.
2. Set the `UID` attribute to an appropriate user name for accessing the Hive server.

## Using User Name And Password

This authentication mechanism requires a user name and a password.

This authentication mechanism is available only for Hive Server 2 on non-HDInsight distributions.

**To configure User Name And Password authentication:**

1. Set the `AuthMech` connection attribute to 3.
2. Set the `UID` attribute to an appropriate user name for accessing the Hive server.
3. Set the `PWD` attribute to the password corresponding to the user name you provided above.
4. Set the `ThriftTransport` connection attribute to the transport protocol to use in the Thrift layer.
5. If the Hive server is configured to use SSL, then configure SSL for the connection. For more information, see [Configuring SSL Verification on a Non-Windows Machine](#) on page 62.

## Using Windows Azure HDInsight Service

This authentication mechanism is available only for Hive Server 2 on HDInsight distributions. When you use this authentication mechanism, you must enable SSL, and HTTP is the only Thrift transport protocol available.

**To configure a connection to a Hive server on Windows Azure HDInsight Service:**

1. Set the `AuthMech` connection attribute to 6.
2. Set the `HTTPPath` attribute to the partial URL corresponding to the Hive server.
3. Set the `UID` attribute to an appropriate user name for accessing the Hive server.
4. Set the `PWD` attribute to the password corresponding to the user name you typed above.
5. If necessary, you can create custom HTTP headers. For more information, see [http.header](#) on page 112.
6. Configure SSL settings as needed. For more information, see [Configuring SSL Verification on a Non-Windows Machine](#) on page 62.

## Delegating Authentication to a Specific User

Some Hive Server 2 instances support the ability to delegate all operations against Hive to the specified user, rather than to the authenticated user for the connection.

**To delegate all operations to a specified user:**

- Set the `DelegationUID` configuration option to the name of the user to be delegated.

If the server returns an error message such as **Failed to validate proxy privilege of `[RealUser]` for `[DelegationUID]`**, you may need to modify the server's `core-site.xml` configuration file, as follows:

1. In the server's `core-site.xml` configuration file, add the following properties:

```
hadoop.proxyuser.[RealUser].groups=*
hadoop.proxyuser.[RealUser].hosts=*
```

Where `[RealUser]` is the authenticated user for the connection.

2. If you are using Kerberos authentication, then in the server's `core-site.xml` configuration file, add the following properties:

```
hadoop.proxyuser.[Principal].groups=*
hadoop.proxyuser.[Principal].hosts=*
```

Where `[Principal]` is the primary Kerberos principal user. For example, if the primary Kerberos principal user is `kerbuser@example.com`, replace `[Principal]` with `kerbuser`.

For more information on resolving this error, see your Hive Server documentation.

## Configuring SSL Verification on a Non-Windows Machine

If you are connecting to a Hive server that has Secure Sockets Layer (SSL) enabled, you can configure the connector to connect to an SSL-enabled socket. When using SSL to connect to a server, the connector supports identity verification between the client (the connector itself) and the server.

### Note:

If the `AuthMech` property is set to 2, SSL is not available.

You can set the connection properties described below in a connection string, in a DSN (in the `odbc.ini` file), or as a connector-wide setting (in the `simba.hiveodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

#### To configure SSL verification on a non-Windows machine:

1. To enable SSL connections, set the `SSL` attribute to 1.
2. To allow authentication using self-signed certificates that have not been added to the list of trusted certificates, set the `AllowSelfSignedServerCert` attribute to 1.
3. To allow the common name of a CA-issued SSL certificate to not match the host name of the Hive server, set the `CAIssuedCertNamesMismatch` attribute to 1.
4. Choose one:
  - To configure the connector to load SSL certificates from a specific `.pem` file when verifying the server, set the `TrustedCerts` attribute to the full path of the `.pem` file.
  - Or, to use the trusted CA certificates `.pem` file that is installed with the connector, do not specify a value for the `TrustedCerts` attribute.
5. To configure two-way SSL verification, set the `TwoWaySSL` attribute to 1 and then do the following:
  - a. Set the `ClientCert` attribute to the full path of the `.pem` file containing the client's certificate.
  - b. Set the `ClientPrivateKey` attribute to the full path of the file containing the client's private key.
  - c. If the private key file is protected with a password, set the `ClientPrivateKeyPassword` attribute to the password.
6. To specify the minimum version of TLS to use, set the `Min_TLS` property to the minimum version of TLS. Supported options include `1.0` for TLS 1.0, `1.1` for TLS 1.1, and `1.2` for TLS 1.2.

## Configuring Server-Side Properties on a Non-Windows Machine

You can use the connector to apply configuration properties to the Hive server.

You can set the connection properties described below in a connection string, in a DSN (in the `odbc.ini` file), or as a connector-wide setting (in the `simba.hiveodbc.ini` file). Settings in the connection string take precedence over

settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

### To configure server-side properties on a non-Windows machine:

1. To set a server-side property, use the syntax `SSP_[SSPKey]=[SSPValue]`, where `[SSPKey]` is the name of the server-side property and `[SSPValue]` is the value to specify for that property. For example, to set the `mapreduce.job.queueName` property to `myQueue`, type the following:

```
SSP_mapreduce.job.queueName=myQueue
```

#### Note:

- When setting a server-side property in a connection string, it is recommended that you enclose the value in braces (`{ }`) to make sure that special characters can be properly escaped.
- For a list of all Hadoop and Hive server-side properties that your implementation supports, type `set -v` at the Hive CLI command line or Beeline. You can also execute the `set -v` query after connecting using the connector.

2. To change the method that the connector uses to apply server-side properties, do one of the following:
  - To configure the connector to apply each server-side property by executing a query when opening a session to the Hive server, set the `ApplySSPWithQueries` property to 1.
  - Or, to configure the connector to use a more efficient method for applying server-side properties that does not involve additional network round-tripping, set the `ApplySSPWithQueries` property to 0.

#### Note:

The more efficient method is not available for Hive Server 1, and it might not be compatible with some Hive Server builds. If the server-side properties do not take effect when the `ApplySSPWithQueries` property is set to 0, then set it to 1.

3. To disable the connector's default behavior of converting server-side property key names to all lower-case characters, set the `LCASESSPKeyName` property to 0.

## Configuring Logging Options on a Non-Windows Machine

To help troubleshoot issues, you can enable logging in the connector.



**! Important:**

Only enable logging long enough to capture an issue. Logging decreases performance and can consume a large quantity of disk space.

You can set the connection properties described below in a connection string, in a DSN (in the `odbc.ini` file), or as a connector-wide setting (in the `simba.hiveodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

**To enable logging on a non-Windows machine:**

1. To specify the level of information to include in log files, set the `LogLevel` property to one of the following numbers:


| LogLevel Value | Description                                                            |
|----------------|------------------------------------------------------------------------|
| 0              | Disables all logging.                                                  |
| 1              | Logs severe error events that lead the connector to abort.             |
| 2              | Logs error events that might allow the connector to continue running.  |
| 3              | Logs events that might result in an error if action is not taken.      |
| 4              | Logs general information that describes the progress of the connector. |
| 5              | Logs detailed information that is useful for debugging the connector.  |
| 6              | Logs all connector activity.                                           |

2. Set the `LogPath` key to the full path to the folder where you want to save log files.
3. Set the `LogFileCount` key to the maximum number of log files to keep.

**Note:**

After the maximum number of log files is reached, each time an additional file is created, the connector deletes the oldest log file.

4. Set the `LogFileSize` key to the maximum size of each log file in bytes.

 **Note:**

After the maximum file size is reached, the connector creates a new file and continues logging.

5. Optionally, to prefix the log file name with the user name and process ID associated with the connection, set the `UseLogPrefix` property to 1.
6. Save the `simba.hiveodbc.ini` configuration file.
7. Restart your ODBC application to make sure that the new settings take effect.

The Simba Apache Hive ODBC Connector produces the following log files at the location you specify using the `LogPath` key:

- A `simbahiveodbcdriver.log` file that logs connector activity that is not specific to a connection.
- A `simbahiveodbcdriver_connection_[Number].log` file for each connection made to the database, where `[Number]` is a number that identifies each log file. This file logs connector activity that is specific to the connection.

If you set the `UseLogPrefix` property to 1, then each file name is prefixed with `[UserName]_[ProcessID]_`, where `[UserName]` is the user name associated with the connection and `[ProcessID]` is the process ID of the application through which the connection is made. For more information, see [UseLogPrefix](#) on page 114.

**To disable logging on a non-Windows machine:**

1. Set the `LogLevel` key to 0.
2. Save the `simba.hiveodbc.ini` configuration file.
3. Restart your ODBC application to make sure that the new settings take effect.

## Setting Connector-Wide Configuration Options on a Non-Windows Machine

When you specify connection settings in a DSN or connection string, those settings apply only when you connect to Hive using that particular DSN or string. As an alternative, you can specify settings that apply to every connection that uses the Simba Apache Hive ODBC Connector by configuring them in the `simba.hiveodbc.ini` file.

 **Note:**

Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

**To set connector-wide configuration options on a non-Windows machine:**

1. In a text editor, open the `simba.hiveodbc.ini` configuration file.
2. In the `[Driver]` section, specify configuration options as key-value pairs. Start a new line for each key-value pair.

For example, to enable User Name authentication using "simba" as the user name, type the following:

```
AuthMech=2
UID=simba
```

For detailed information about all the configuration options supported by the connector, see [Connector Configuration Options](#) on page 81.

3. Save the `simba.hiveodbc.ini` configuration file.

## Testing the Connection on a Non-Windows Machine

To test the connection, you can use an ODBC-enabled client application. For a basic connection test, you can also use the test utilities that are packaged with your driver manager installation. For example, the iODBC driver manager includes simple utilities called `iodbctest` and `iodbctestw`. Similarly, the unixODBC driver manager includes simple utilities called `isql` and `iusql`.

### Using the iODBC Driver Manager

You can use the `iodbctest` and `iodbctestw` utilities to establish a test connection with your connector. Use `iodbctest` to test how your connector works with an ANSI application, or use `iodbctestw` to test how your connector works with a Unicode application.

**Note:**

There are 32-bit and 64-bit installations of the iODBC driver manager available. If you have only one or the other installed, then the appropriate version of `iodbctest` (or `iodbctestw`) is available. However, if you have both 32- and 64-bit versions installed, then you need to make sure that you are running the version from the correct installation directory.

For more information about using the iODBC driver manager, see <http://www.iodbc.org>.

**To test your connection using the iODBC driver manager:**

1. Run `iodbctest` or `iodbctestw`.
2. Optionally, if you do not remember the DSN, then type a question mark (?) to see a list of available DSNs.
3. Type the connection string for connecting to your data store, and then press ENTER. For more information, see .

If the connection is successful, then the `SQL>` prompt appears.

## Using the unixODBC Driver Manager

You can use the `isql` and `iusql` utilities to establish a test connection with your connector and your DSN. `isql` and `iusql` can only be used to test connections that use a DSN. Use `isql` to test how your connector works with an ANSI application, or use `iusql` to test how your connector works with a Unicode application.

 **Note:**

There are 32-bit and 64-bit installations of the unixODBC driver manager available. If you have only one or the other installed, then the appropriate version of `isql` (or `iusql`) is available. However, if you have both 32- and 64-bit versions installed, then you need to make sure that you are running the version from the correct installation directory.

For more information about using the unixODBC driver manager, see <http://www.unixodbc.org>.

**To test your connection using the unixODBC driver manager:**

- Run `isql` or `iusql` by using the corresponding syntax:

- `isql [DataSourceName]`
- `iusql [DataSourceName]`

`[DataSourceName]` is the DSN that you are using for the connection.

If the connection is successful, then the `SQL>` prompt appears.

 **Note:**

For information about the available options, run `isql` or `iusql` without providing a DSN.

## Authentication Mechanisms

To connect to a Hive server, you must configure the Simba Apache Hive ODBC Connector to use the authentication mechanism that matches the access requirements of the server and provides the necessary credentials. To determine the authentication settings that your Hive server requires, check the server configuration and then refer to the corresponding section below.

### Hive Server 1

You must use No Authentication as the authentication mechanism. Hive Server 1 instances do not support authentication.

### Hive Server 2 on an HDInsight Distribution

If you are connecting to HDInsight Service running on Windows Azure, then you must use the Windows Azure HDInsight Service mechanism.

### Hive Server 2 on a non-HDInsight Distribution

**Note:**

Most default configurations of Hive Server 2 on non-HDInsight distributions require User Name authentication.

Configuring authentication for a connection to a Hive Server 2 instance on a non-HDInsight Distribution involves setting the authentication mechanism, the Thrift transport protocol, and SSL support. To determine the settings that you need to use, check the following three properties in the `hive-site.xml` file in the Hive server that you are connecting to:

- `hive.server2.authentication`
- `hive.server2.transport.mode`
- `hive.server2.use.SSL`

Use the following table to determine the authentication mechanism that you need to configure, based on the `hive.server2.authentication` value in the `hive-site.xml` file:

| <code>hive.server2.authentication</code> | Authentication Mechanism |
|------------------------------------------|--------------------------|
| NOSASL                                   | No Authentication        |
| KERBEROS                                 | Kerberos                 |
| NONE                                     | User Name                |
| LDAP                                     | User Name and Password   |
| SAML                                     | SAML 2.0                 |

Use the following table to determine the Thrift transport protocol that you need to configure, based on the `hive.server2.authentication` and `hive.server2.transport.mode` values in the `hive-site.xml` file:

| <code>hive.server2.authentication</code> | <code>hive.server2.transport.mode</code> | Thrift Transport Protocol |
|------------------------------------------|------------------------------------------|---------------------------|
| NOSASL                                   | binary                                   | Binary                    |
| KERBEROS                                 | binary or http                           | SASL or HTTP              |
| NONE                                     | binary or http                           | SASL or HTTP              |
| LDAP                                     | binary or http                           | SASL or HTTP              |
| SAML                                     | http                                     | HTTP                      |

To determine whether SSL should be enabled or disabled for your connection, check the `hive.server2.use.SSL` value in the `hive-site.xml` file. If the value is true, then you must enable and configure SSL in your connection. If the value is false, then you must disable SSL in your connection.

For detailed instructions on how to configure authentication when using the Windows connector, see [Configuring Authentication on Windows](#) on page 15.

For detailed instructions on how to configure authentication when using a non-Windows connector, see [Configuring Authentication on a Non-Windows Machine](#) on page 58.

## Using a Connection String

For some applications, you might need to use a connection string to connect to your data source. For detailed information about how to use a connection string in an ODBC application, refer to the documentation for the application that you are using.

The connection strings in the following sections are examples showing the minimum set of connection attributes that you must specify to successfully connect to the data source. Depending on the configuration of the data source and the type of connection you are working with, you might need to specify additional connection attributes. For detailed information about all the attributes that you can use in the connection string, see [Connector Configuration Options](#) on page 81.

### DSN Connection String Example

The following is an example of a connection string for a connection that uses a DSN:

```
DSN= [DataSourceName]
```

*[DataSourceName]* is the DSN that you are using for the connection.

You can set additional configuration options by appending key-value pairs to the connection string. Configuration options that are passed in using a connection string take precedence over configuration options that are set in the DSN.

### DSN-less Connection String Examples

Some applications provide support for connecting to a data source using a connector without a DSN. To connect to a data source without using a DSN, use a connection string instead.

The placeholders in the examples are defined as follows, in alphabetical order:

- *[DomainName]* is the fully qualified domain name of the Hive server host.
- *[Namespace]* is the namespace on ZooKeeper under which Hive Server 2 znodes are added.
- *[PortNumber]* is the number of the TCP port that the Hive server uses to listen for client connections.
- *[Realm]* is the Kerberos realm of the Hive server host.
- *[Server]* is the IP address or host name of the Hive server to which you are connecting.
- *[ServerURL]* is the partial URL corresponding to the Hive server.

- *[ServiceName]* is the Kerberos service principal name of the Hive server.
- *[YourPassword]* is the password corresponding to your user name.
- *[YourUserName]* is the user name that you use to access the Hive server.

## Connecting to a Hive Server 1 Instance

The following is the format of a DSN-less connection string that connects to a Hive Server 1 instance:

```
Driver=Simba Hive ODBC Driver;HiveServerType=1;  
Host=[Server];Port=[PortNumber];
```

For example:

```
Driver=Simba Hive ODBC Driver;HiveServerType=1;  
Host=192.168.222.160;Port=10000;
```

## Connecting to a Standard Hive Server 2 Instance

The following is the format of a DSN-less connection string for a standard connection to a Hive Server 2 instance. By default, the connector is configured to connect to a Hive Server 2 instance that requires User Name authentication, and the connector uses **anonymous** as the user name.

```
Driver=Simba Hive ODBC Driver;Host=[Server];  
Port=[PortNumber];
```

For example:

```
Driver=Simba Hive ODBC Driver;Host=192.168.222.160;  
Port=10000;
```

## Connecting using Dynamic Service Discovery

The following is the format of a DSN-less connection string that discovers Hive Server 2 services via the ZooKeeper service.

```
Driver=Simba Hive ODBC Driver;ServiceDiscoveryMode=1;  
Host=[Server1]:[PortNumber1], [Server2]:[PortNumber2],  
[Server3]:[PortNumber3];ZKNamespace=[Namespace];
```

For example:

```
Driver=Simba Hive ODBC Driver;ServiceDiscoveryMode=1;  
Host=192.168.222.160:10000, 192.168.222.165:10000,
```



```
192.168.222.231:10000;ZKNamespace=hiveserver;
```

## Connecting to a Hive Server 2 Instance Without Authentication

The following is the format of a DSN-less connection string for a Hive Server 2 instance that does not require authentication.

```
Driver=Simba Hive ODBC Driver;Host=[Server];  
Port=[PortNumber];AuthMech=0;
```

For example:

```
Driver=Simba Hive ODBC Driver;Host=192.168.222.160;  
Port=10000;AuthMech=0;
```

## Connecting to a Hive Server that Requires Kerberos Authentication

The following is the format of a DSN-less connection string that connects to a Hive Server 2 instance requiring Kerberos authentication:

```
Driver=Simba Hive ODBC Driver;Host=[Server];  
Port=[PortNumber];AuthMech=1;KrbRealm=[Realm];  
KrbHostFQDN=[DomainName];KrbServiceName=[ServiceName];
```

For example:

```
Driver=Simba Hive ODBC Driver;Host=192.168.222.160;  
Port=10000;AuthMech=1;KrbRealm=SIMBA;  
KrbHostFQDN=localhost.localdomain;KrbServiceName=hive;
```

## Connecting to a Hive Server using SAML 2.0

The following is the format of a DSN-less connection string that connects to a Hive Server 2 instance via Single Sign-On using SAML 2.0 authentication:

```
Driver=SimbaHive ODBC Driver;Host=[Server];  
Port=[PortNumber];AuthMech=12;ThriftTransport=2;HTTPPath=  
[ServerURL];SSL=1;
```

For example:

```
Driver=SimbaHive ODBC Driver;Host=192.168.222.160;  
Port=10000;AuthMech=12;ThriftTransport=2;HTTPPath=cliservice  
;SSL=1;
```

## Connecting to a Hive Server that Requires User Name And Password Authentication (LDAP)

The following is the format of a DSN-less connection string that connects to a Hive Server 2 instance requiring User Name And Password authentication:

```
Driver=Simba Hive ODBC Driver;Host=[Server];  
Port=[PortNumber];AuthMech=3;UID=[YourUserName];  
PWD=[YourPassword];
```

For example:

```
Driver=Simba Hive ODBC Driver;Host=192.168.222.160;  
Port=10000;AuthMech=3;UID=simba;PWD=simba;
```

## Connecting to a Hive Server on Windows Azure HDInsight Service

The following is the format of a DSN-less connection string that connects to a Hive Server 2 instance running on Windows Azure HDInsight Service:

```
Driver=Simba Hive ODBC Driver;Host=[Server];  
Port=[PortNumber];AuthMech=6;SSL=1;UID=[YourUserName];  
PWD=[YourPassword];HTTPPath=[ServerURL];
```

For example:

```
Driver=Simba Hive ODBC Driver;Host=192.168.222.160;  
Port=10000;AuthMech=6;SSL=1;UID=simba;PWD=simba;  
HTTPPath=gateway/sandbox/hive;
```

## Features

For more information on the features of the Simba Apache Hive ODBC Connector, see the following:

- [SQL Connector for HiveQL](#) on page 75
- [Data Types](#) on page 76
- [Catalog and Schema Support](#) on page 77
- [hive\\_system Table](#) on page 77
- [Server-Side Properties](#) on page 78
- [Get Tables With Query](#) on page 78
- [Active Directory](#) on page 78
- [Write-back](#) on page 79
- [Timestamp Function Support](#) on page 79
- [Dynamic Service Discovery using ZooKeeper](#) on page 79
- [Security and Authentication](#) on page 80

## SQL Connector for HiveQL

The native query language supported by Hive is HiveQL. For simple queries, HiveQL is a subset of SQL-92. However, the syntax is different enough that most applications do not work with native HiveQL.


To bridge the difference between SQL and HiveQL, the SQL Connector feature translates standard SQL-92 queries into equivalent HiveQL queries. The SQL Connector performs syntactical translations and structural transformations. For example:


- **Quoted Identifiers:** The double quotes (") that SQL uses to quote identifiers are translated into back quotes (`) to match HiveQL syntax. The SQL Connector needs to handle this translation because even when a connector reports the back quote as the quote character, some applications still generate double-quoted identifiers.
- **Table Aliases:** Support is provided for the AS keyword between a table reference and its alias, which HiveQL normally does not support.
- **JOIN, INNER JOIN, and CROSS JOIN:** SQL JOIN, INNER JOIN, and CROSS JOIN syntax is translated to HiveQL JOIN syntax.
- **TOP N/LIMIT:** SQL TOP N queries are transformed to HiveQL LIMIT queries.


## Data Types

The Simba Apache Hive ODBC Connector supports many common data formats, converting between Hive data types and SQL data types.

The following table lists the supported data type mappings.

| Hive Type    | SQL Type                                                                                                                                                                                                                                                          |
|--------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| BIGINT       | SQL_BIGINT                                                                                                                                                                                                                                                        |
| BINARY       | SQL_VARBINARY                                                                                                                                                                                                                                                     |
| BOOLEAN      | SQL_BIT                                                                                                                                                                                                                                                           |
| CHAR(n)      | SQL_CHAR                                                                                                                                                                                                                                                          |
|              | <p> <b>Note:</b></p> <p>SQL_WCHAR is returned instead if the Unicode SQL Character Types configuration option (the <code>UseUnicodeSqlCharacterTypes</code> key) is enabled.</p> |
| DATE         | SQL_TYPE_DATE                                                                                                                                                                                                                                                     |
| DECIMAL      | SQL_DECIMAL                                                                                                                                                                                                                                                       |
| DECIMAL(p,s) | SQL_DECIMAL                                                                                                                                                                                                                                                       |
| DOUBLE       | SQL_DOUBLE                                                                                                                                                                                                                                                        |
| FLOAT        | SQL_REAL                                                                                                                                                                                                                                                          |
| INT          | SQL_INTEGER                                                                                                                                                                                                                                                       |
| SMALLINT     | SQL_SMALLINT                                                                                                                                                                                                                                                      |

| Hive Type  | SQL Type                                                                                                                                                                                                                                                                                                                                                      |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| STRING     | SQL_VARCHAR<br><div style="border: 1px solid black; padding: 5px; margin-top: 5px;"> <p> <b>Note:</b><br/>SQL_WVARCHAR is returned instead if the Unicode SQL Character Types configuration option (the <code>UseUnicodeSqlCharacterTypes</code> key) is enabled.</p> </div> |
| TIMESTAMP  | SQL_TYPE_TIMESTAMP                                                                                                                                                                                                                                                                                                                                            |
| TINYINT    | SQL_TINYINT                                                                                                                                                                                                                                                                                                                                                   |
| VARCHAR(n) | SQL_VARCHAR                                                                                                                                                                                                                                                                                                                                                   |

 **Note:**

The aggregate types (ARRAY, MAP, and STRUCT) are not supported. Columns of aggregate types are treated as STRING columns.

The interval types (YEAR TO MONTH and DAY TIME) are supported only in query expressions and predicates. Interval types are not supported as column data types in tables.

## Catalog and Schema Support

The Simba Apache Hive ODBC Connector supports both catalogs and schemas to make it easy for the connector to work with various ODBC applications. Since Hive only organizes tables into schemas/databases, the connector provides a synthetic catalog named HIVE under which all of the schemas/databases are organized. The connector also maps the ODBC schema to the Hive schema/database.

## hive\_system Table

A pseudo-table called `hive_system` can be used to query for Hive cluster system environment information. The pseudo-table is under the pseudo-schema called `hive_system`. The table has two STRING type columns, `envkey` and `envvalue`. Standard SQL can be executed against the `hive_system` table. For example:

```
SELECT * FROM HIVE.hive_system.hive_system WHERE envkey LIKE '%hive%'
```

The above query returns all of the Hive system environment entries whose key contains the word "hive". A special query, `set -v`, is executed to fetch system environment information. Some versions of Hive do not support this query. For versions of Hive that do not support querying system environment information, the connector returns an empty result set.

## Server-Side Properties

The Simba Apache Hive ODBC Connector allows you to set server-side properties via a DSN. Server-side properties specified in a DSN affect only the connection that is established using the DSN.

You can also specify server-side properties for connections that do not use a DSN. To do this, use the Simba Hive ODBC Driver Configuration tool that is installed with the Windows version of the connector, or set the appropriate configuration options in your connection string or the `simba.hiveodbc.ini` file. Properties specified in the connector configuration tool or the `simba.hiveodbc.ini` file apply to all connections that use the Simba Apache Hive ODBC Connector.

For more information about setting server-side properties when using the Windows connector, see [Configuring Server-Side Properties on Windows](#) on page 26. For information about setting server-side properties when using the connector on a non-Windows platform, see [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 63.

## Get Tables With Query

The Get Tables With Query configuration option allows you to choose whether to use the SHOW TABLES query or the GetTables API call to retrieve table names from a database.

## Active Directory

The Simba Apache Hive ODBC Connector supports Active Directory Kerberos on Windows. There are two prerequisites for using Active Directory Kerberos on Windows:

- MIT Kerberos is not installed on the client Windows machine.
- The MIT Kerberos Hadoop realm has been configured to trust the Active Directory realm so that users in the Active Directory realm can access services in the MIT Kerberos Hadoop realm.

## Write-back

The Simba Apache Hive ODBC Connector supports translation for the following syntax when connecting to a Hive Server 2 instance:

- INSERT
- UPDATE
- DELETE
- CREATE
- DROP

If the statement contains non-standard SQL-92 syntax, then the connector is unable to translate the statement to SQL and instead falls back to using HiveQL.

## Timestamp Function Support

The Simba Apache Hive ODBC Connector supports the following ODBC functions for working with data of type `TIMESTAMP`:

- **TIMESTAMPADD**: You can call this function to increment a `TIMESTAMP` value by a specified interval of time.
- **TIMESTAMPDIFF**: You can call this function to calculate the interval of time between two specified `TIMESTAMP` values.

The types of time intervals that are supported for these functions might vary depending on the Hive server version that you are connecting to. To return a list of the intervals supported for `TIMESTAMPADD`, call the `SQLGetInfo` catalog function using `SQL_TIMEDATE_ADD_INTERVALS` as the argument. Similarly, to return a list of the intervals supported for `TIMESTAMPDIFF`, call `SQLGetInfo` using `SQL_TIMEDATE_DIFF_INTERVALS` as the argument.

 **Note:**

The `SQL_TSI_FRAC_SECOND` interval is not supported by Hive.

## Dynamic Service Discovery using ZooKeeper

The Simba Apache Hive ODBC Connector can be configured to discover Hive Server 2 services via the ZooKeeper service.

For information about configuring this feature in the Windows connector, see [Creating a Data Source Name on Windows](#) on page 9 or [Configuring a DSN-less Connection on Windows](#) on page 12. For information about configuring this feature when using the

connector on a non-Windows platform, see [Configuring Service Discovery Mode on a Non-Windows Machine](#) on page 57.

## Security and Authentication

To protect data from unauthorized access, some Hive data stores require connections to be authenticated with user credentials or encrypted using the SSL protocol. The Simba Apache Hive ODBC Connector provides full support for these authentication protocols.



### Note:

In this documentation, "SSL" refers to both TLS (Transport Layer Security) and SSL (Secure Sockets Layer). The connector supports TLS 1.0, 1.1, and 1.2. The SSL version used for the connection is the highest version that is supported by both the connector and the server.

The connector provides mechanisms that enable you to authenticate your connection using the Kerberos protocol, your Hive user name only, or your Hive user name and password. You can also authenticate a connection to an HDInsight distribution on Windows Azure. You must use the authentication mechanism that matches the security requirements of the Hive server. For information about determining the appropriate authentication mechanism to use based on the Hive server configuration, see [Authentication Mechanisms](#) on page 69. For detailed connector configuration instructions, see [Configuring Authentication on Windows](#) on page 15 or [Configuring Authentication on a Non-Windows Machine](#) on page 58.

Additionally, the connector supports the following types of SSL connections:

- No identity verification
- One-way authentication
- Two-way authentication

It is recommended that you enable SSL whenever you connect to a server that is configured to support it. SSL encryption protects data and credentials when they are transferred over the network, and provides stronger security than authentication alone. For detailed configuration instructions, see [Configuring SSL Verification on Windows](#) on page 25 or [Configuring SSL Verification on a Non-Windows Machine](#) on page 62.



## Connector Configuration Options

Connector Configuration Options lists the configuration options available in the Simba Apache Hive ODBC Connector alphabetically by field or button label. Options having only key names, that is, not appearing in the user interface of the connector, are listed alphabetically by key name.

When creating or configuring a connection from a Windows machine, the fields and buttons are available in the Simba Hive ODBC Driver Configuration tool and the following dialog boxes:

- Simba Hive ODBC Connector DSN Setup
- Advanced Options
- HTTP Proxy Options
- Server Side Properties
- SSL Options
- HTTP Properties

When using a connection string or configuring a connection from a non-Windows machine, use the key names provided.

### Note:

If you are using the connector on a non-Windows machine, you can set connector configuration properties in a connection string, in a DSN (in the `odbc.ini` file), or as a connector-wide setting (in the `simba.hiveodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over connector-wide settings.

## Configuration Options Appearing in the User Interface

The following configuration options are accessible via the Windows user interface for the Simba Apache Hive ODBC Connector, or via the key name when using a connection string or configuring a connection from a Linux/macOS/AIX/Solaris/Debian machine:

- [Allow Common Name Host Name Mismatch](#) on page 83
- [Allow Self-Signed Server](#)
- [Log Path](#) on page 96
- [Max File Size](#) on page 97
- [Max Number Files](#) on page 97

- [Certificate](#) on page 83
- [Apply Properties with Queries](#) on page 84
- [Async Exec Poll Interval](#) on page 84
- [Authentication Flow](#) on page 85
- [Binary Column Length](#) on page 85
- [Canonicalize Principal FQDN](#) on page 85
- [CheckCertificate Revocation](#) on page 86
- [Client Certificate File](#) on page 87
- [Client Private Key File](#) on page 87
- [Client Private Key Password](#) on page 88
- [Convert Key Name to Lower Case](#) on page 88
- [Database](#) on page 88
- [Decimal Column Scale](#) on page 89
- [Default String Column Length](#) on page 89
- [Delegate Kerberos Credentials](#) on page 89
- [Delegation UID](#) on page 90
- [Driver Config Take Precedence](#) on page 90
- [Enable Auto Reconnect](#) on page 91
- [Enable SSL](#) on page 91
- [Fast SQLPrepare](#) on page 92
- [Get Tables With Query](#) on page 92
- [Hive Server Type](#) on page 93
- [Host\(s\)](#) on page 93
- [Host FQDN](#) on page 93
- [HTTP Path](#) on page 94
- [Ignore SQL\\_DRIVER\\_NOPROMPT](#) on page 94
- [Mechanism](#) on page 98
- [Minimum TLS](#) on page 98
- [Password](#) on page 99
- [Port](#) on page 99
- [Proxy Host](#) on page 99
- [Proxy Password](#) on page 100
- [Proxy Port](#) on page 100
- [Proxy Username](#) on page 100
- [Realm](#) on page 101
- [Rows Fetched Per Block](#) on page 101
- [Save Password \(Encrypted\)](#) on page 101
- [Service Discovery Mode](#) on page 102
- [Service Name](#) on page 102
- [Show System Table](#) on page 102
- [Socket Timeout](#) on page 103
- [Thrift Transport](#) on page 103
- [Trusted Certificates](#) on page 104
- [Two-Way SSL](#) on page 105
- [Unicode SQL Character Types](#) on page 105
- [Use Async Exec](#) on page 106
- [Use Native Query](#) on page 106
- [Use Only SSPI](#) on page 106
- [Use Proxy Server](#) on page 107
- [Use System Trust Store](#) on page 107
- [User Name](#) on page 108
- [ZK Force Active Passive HA](#) on page 109
- [ZooKeeper Namespace](#) on page 109

- [Invalid Session Auto Recover](#) on page 95
- [Log Level](#) on page 95

## Allow Common Name Host Name Mismatch

| Key Name                  | Default Value | Required |
|---------------------------|---------------|----------|
| CAIssuedCertNamesMismatch | Clear (0)     | No       |

### Description

This option specifies whether a CA-issued SSL certificate name must match the host name of the Hive server.

- Enabled (1): The connector allows a CA-issued SSL certificate name to not match the host name of the Hive server.
- Disabled (0): The CA-issued SSL certificate name must match the host name of the Hive server.



#### Note:

This setting is applicable only when SSL is enabled.

## Allow Self-Signed Server Certificate


| Key Name                      | Default Value | Required |
|-------------------------------|---------------|----------|
| AllowSelfSigned<br>ServerCert | Clear (0)     | No       |

### Description

This option specifies whether the connector allows a connection to a Hive server that uses a self-signed certificate, even if this certificate is not in the list of trusted certificates. This list is contained in the Trusted Certificates file, or in the system Trust Store if the system Trust Store is used instead of a file.

- Enabled (1): The connector authenticates the Hive server even if the server is using a self-signed certificate that has not been added to the list of trusted certificates.

- Disabled (0): The connector does not allow self-signed certificates from the server unless they have already been added to the list of trusted certificates.

 **Note:**

This setting is applicable only when SSL is enabled.

## Apply Properties with Queries

| Key Name            | Default Value | Required |
|---------------------|---------------|----------|
| ApplySSPWithQueries | Selected (1)  | No       |

### Description

This option specifies how the connector applies server-side properties.

- Enabled (1): The connector applies each server-side property by executing a `set SSPKey=SSPValue` query when opening a session to the Hive server.
- Disabled (0): The connector uses a more efficient method for applying server-side properties that does not involve additional network round-tripping. However, some Hive Server 2 builds are not compatible with the more efficient method.

 **Note:**

When connecting to a Hive Server 1 instance, this option is always enabled.


## Async Exec Poll Interval

| Key Name              | Default Value | Required |
|-----------------------|---------------|----------|
| AsyncExecPollInterval | 100           | No       |

### Description

The time in milliseconds between each poll for the query execution status.

"Asynchronous execution" refers to the fact that the RPC call used to execute a query against Hive is asynchronous. It does not mean that ODBC asynchronous operations are supported.

 **Note:**


This option is applicable only to HDInsight clusters.

## Authentication Flow

| Key Name  | Default Value | Required |
|-----------|---------------|----------|
| Auth_Flow | browser       | No       |

## Description

This property specifies the type of authentication flow that the connector uses when the Mechanism option is set to SAML\_2.0. Currently, the only supported value is `browser`.

 **Note:**

The browser workflow is only supported in a GUI desktop environment on Windows, Linux, and macOS.

## Binary Column Length

| Key Name           | Default Value | Required |
|--------------------|---------------|----------|
| BinaryColumnLength | 32767         | No       |

## Description

The maximum data length for BINARY columns.

By default, the columns metadata for Hive does not specify a maximum data length for BINARY columns.

## Canonicalize Principal FQDN

| Key Name                          | Default Value | Required |
|-----------------------------------|---------------|----------|
| ServicePrincipal Canonicalization | Selected (1)  | No       |

## Description

This option specifies whether the Kerberos layer canonicalizes the host FQDN in the server's service principal name.

- Enabled (1): The Kerberos layer canonicalizes the host FQDN in the server's service principal name.
- Disabled (0): The Kerberos layer does not canonicalize the host FQDN in the server's service principal name.

### Note:

- This option only affects MIT Kerberos, and is ignored when using Active Directory Kerberos.
- This option can only be disabled if the Kerberos Realm or `KrbRealm` key is specified.

## CheckCertificate Revocation

| Key Name                         | Default Value | Required |
|----------------------------------|---------------|----------|
| <code>CheckCertRevocation</code> | Selected (1)  | No       |

## Description

This option specifies whether the connector checks to see if a certificate has been revoked while retrieving a certificate chain from the Windows Trust Store.

This option is only applicable if you are using a CA certificate from the Windows Trust Store (see [Use System Trust Store](#) on page 107).

- Enabled (1): The connector checks for certificate revocation while retrieving a certificate chain from the Windows Trust Store.
- Disabled (0): The connector does not check for certificate revocation while retrieving a certificate chain from the Windows Trust Store.

### Note:

This property is disabled when the `AllowSelfSignedServerCert` property is set to 1.

### Note:

This option is only available on Windows.

## Client Certificate File

| Key Name   | Default Value | Required |
|------------|---------------|----------|
| ClientCert | None          | No       |

### Description

The full path to the `.pem` file containing the client's SSL certificate.

**Note:**

This setting is applicable only when two-way SSL is enabled.

## Client Private Key File

| Key Name         | Default Value | Required                                     |
|------------------|---------------|----------------------------------------------|
| ClientPrivateKey | None          | Yes, if two-way SSL verification is enabled. |

### Description

The full path to the `.pem` file containing the client's SSL private key.

If the private key file is protected with a password, then provide the password using the connector configuration option [Client Private Key Password](#) on page 88.

**Note:**

This setting is applicable only when two-way SSL is enabled.

## Client Private Key Password

| Key Name                 | Default Value | Required                                                                                                    |
|--------------------------|---------------|-------------------------------------------------------------------------------------------------------------|
| ClientPrivateKeyPassword | None          | Yes, if two-way SSL verification is enabled and the client's private key file is protected with a password. |

### Description

The password of the private key file that is specified in the Client Private Key File field (ClientPrivateKey).

## Convert Key Name to Lower Case

| Key Name        | Default Value | Required |
|-----------------|---------------|----------|
| LCaseSspKeyName | Selected (1)  | No       |

### Description

This option specifies whether the connector converts server-side property key names to all lower-case characters.

- Enabled (1): The connector converts server-side property key names to all lower-case characters.
- Disabled (0): The connector does not modify the server-side property key names.

## Database

| Key Name | Default Value | Required |
|----------|---------------|----------|
| Schema   | default       | No       |



## Description

The name of the database schema to use when a schema is not explicitly specified in a query. You can still issue queries on other schemas by explicitly specifying the schema in the query.



### Note:

To inspect your databases and determine the appropriate schema to use, at the Hive command prompt, type `show databases`.

## Decimal Column Scale

| Key Name           | Default Value | Required |
|--------------------|---------------|----------|
| DecimalColumnScale | 10            | No       |

## Description

The maximum number of digits to the right of the decimal point for numeric data types.

## Default String Column Length

| Key Name                  | Default Value | Required |
|---------------------------|---------------|----------|
| DefaultStringColumnLength | 255           | No       |

## Description

The maximum number of characters that can be contained in STRING columns.

By default, the columns metadata for Hive does not specify a maximum length for STRING columns.

## Delegate Kerberos Credentials

| Key Name         | Default Value | Required |
|------------------|---------------|----------|
| DelegateKrbCreds | Clear (0)     | No       |

## Description

This option specifies whether your Kerberos credentials are forwarded to the server and used for authentication.

### Note:

This option is only applicable when Authentication Mechanism is set to Kerberos (AuthMech=1).

## Delegation UID

| Key Name      | Default Value | Required |
|---------------|---------------|----------|
| DelegationUID | None          | No       |

## Description

If a value is specified for this setting, the connector delegates all operations against Hive to the specified user, rather than to the authenticated user for the connection.

### Note:

This option is applicable only when connecting to a Hive Server 2 instance that supports this feature.

## Driver Config Take Precedence

| Key Name                   | Default Value | Required |
|----------------------------|---------------|----------|
| DriverConfigTakePrecedence | Clear (0)     | No       |

## Description

This option specifies whether connector-wide configuration settings take precedence over connection and DSN settings.

- Enabled (1): Connector-wide configurations take precedence over connection and DSN settings.
- Disabled (0): Connection and DSN settings take precedence instead.

## Enable Auto Reconnect

| Key Name      | Default Value | Required |
|---------------|---------------|----------|
| AutoReconnect | Selected (1)  | Yes      |

### Description

This option specifies whether the connector attempts to automatically reconnect to the server when a communication link error occurs.

- Enabled (1): The connector attempts to reconnect.
- Disabled (0): The connector does not attempt to reconnect.

## Enable SSL

| Key Name | Default Value | Required |
|----------|---------------|----------|
| SSL      | Clear (0)     | No       |

### Description

This option specifies whether the client uses an SSL encrypted connection to communicate with the Hive server.

- Enabled (1): The client communicates with the Hive server using SSL.
- Disabled (0): SSL is disabled.

SSL is configured independently of authentication. When authentication and SSL are both enabled, the connector performs the specified authentication method over an SSL connection.

#### Note:

- This option is applicable only when connecting to a Hive server that supports SSL.
- If you selected User Name as the authentication mechanism, SSL is not available.

## Fast SQLPrepare

| Key Name       | Default Value | Required |
|----------------|---------------|----------|
| FastSQLPrepare | Clear (0)     | No       |

### Description

This option specifies whether the connector defers query execution to SQLExecute.

- Enabled (1): The connector defers query execution to SQLExecute.
- Disabled (0): The connector does not defer query execution to SQLExecute.



#### Note:

When using Native Query mode, the connector executes the HiveQL query to retrieve the result set metadata for SQLPrepare. As a result, SQLPrepare might be slow. If the result set metadata is not required after calling SQLPrepare, then enable Fast SQLPrepare.

## Get Tables With Query

| Key Name           | Default Value | Required |
|--------------------|---------------|----------|
| GetTablesWithQuery | 0             | No       |

### Description

This option specifies whether the connector uses the SHOW TABLES query or the GetTables Thrift API call to retrieve table names from the database.

- Enabled (1): The connector uses the SHOW TABLES query to retrieve table names.
- Disabled (0): The connector uses the GetTables Thrift API call to retrieve table names.



#### Note:

This option is applicable only when connecting to a Hive Server 2 instance.

## Hive Server Type

| Key Name       | Default Value     | Required |
|----------------|-------------------|----------|
| HiveServerType | Hive Server 2 (2) | No       |

### Description

This option specifies the type of Hive server.

- Hive Server 1 (1): The connector connects to a Hive Server 1 instance.
- Hive Server 2 (2): The connector connects to a Hive Server 2 instance.



#### Note:

If Service Discovery Mode is enabled, then connections to Hive Server 1 are not supported.

## Host(s)

| Key Name | Default Value | Required |
|----------|---------------|----------|
| Host     | None          | Yes      |

### Description

If Service Discovery Mode is disabled, the IP address or host name of the Hive server.

If Service Discovery Mode is enabled, specify a comma-separated list of ZooKeeper servers in the following format, where *[ZK\_Host]* is the IP address or host name of the ZooKeeper server and *[ZK\_Port]* is the number of the TCP port that the ZooKeeper server uses to listen for client connections:

```
[ZK_Host1]:[ZK_Port1],[ZK_Host2]:[ZK_Port2]
```

## Host FQDN

| Key Name    | Default Value | Required |
|-------------|---------------|----------|
| KrbHostFQDN | _HOST         | No       |

## Description

The fully qualified domain name of the Hive Server 2 host.

When the value of Host FQDN is `_HOST`, the connector uses the Hive server host name as the fully qualified domain name for Kerberos authentication. If Service Discovery Mode is disabled, then the connector uses the value specified in the Host connection attribute. If Service Discovery Mode is enabled, then the connector uses the Hive Server 2 host name returned by ZooKeeper.

## HTTP Path

| Key Name | Default Value                                                                                                                                                           | Required |
|----------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------|
| HTTPPath | <code>/hive2</code> if using Windows Azure HDInsight Service (6).<br><code>/</code> if using non-Windows Azure HDInsight Service with Thrift Transport set to HTTP (2). | No       |

## Description

The partial URL corresponding to the Hive server.

The connector forms the HTTP address to connect to by appending the HTTP Path value to the host and port specified in the DSN or connection string. For example, to connect to the HTTP address

`http://localhost:10002/gateway/sandbox/hive/version`, you would set HTTP Path to `/gateway/sandbox/hive/version`.

### Note:

By default, Hive servers use `cliservice` as the partial URL.

## Ignore SQL\_DRIVER\_NOPROMPT

| Key Name                | Default Value      | Required |
|-------------------------|--------------------|----------|
| SSOIgnoreDriverNoPrompt | <code>false</code> | No       |

## Description

This option specifies whether the connector displays a web browser when the application makes a `SQLDriverConnect` API call with a `SQL_DRIVER_NOPROMPT` flag to the connector.

- Enabled (`true`): The connector displays the web browser used to complete the browser based authentication flow even when `SQL_DRIVER_NOPROMPT` is passed.
- Disabled (`false`): The connector does not display a web browser.

## Invalid Session Auto Recover

| Key Name                               | Default Value | Required |
|----------------------------------------|---------------|----------|
| <code>InvalidSessionAutoRecover</code> | Selected (1)  | No       |

## Description

This option specifies whether the connector automatically opens a new session when the existing session is no longer valid.

- Enabled (1): The connector automatically opens a new session when the existing session is no longer valid.
- Disabled (0): The connector does not automatically open new sessions.

### Note:

This option is applicable only when connecting to Hive Server 2.

## Log Level

| Key Name              | Default Value | Required |
|-----------------------|---------------|----------|
| <code>LogLevel</code> | OFF (0)       | No       |

## Description

Use this property to enable or disable logging in the connector and to specify the amount of detail included in log files.

**! Important:**

- Only enable logging long enough to capture an issue. Logging decreases performance and can consume a large quantity of disk space.
- When logging with connection strings and DSNs, this option only applies to per-connection logs.

Set the property to one of the following values:

- OFF (0): Disable all logging.
- FATAL (1): Logs severe error events that lead the connector to abort.
- ERROR (2): Logs error events that might allow the connector to continue running.
- WARNING (3): Logs events that might result in an error if action is not taken.
- INFO (4): Logs general information that describes the progress of the connector.
- DEBUG (5): Logs detailed information that is useful for debugging the connector.
- TRACE (6): Logs all connector activity.

When logging is enabled, the connector produces the following log files at the location you specify in the Log Path (`LogPath`) property:

- A `simbahiveodbcdriver.log` file that logs connector activity that is not specific to a connection.
- A `simbahiveodbcdriver_connection_[Number].log` file for each connection made to the database, where *[Number]* is a number that identifies each log file. This file logs connector activity that is specific to the connection.

If you enable the `UseLogPrefix` connection property, the connector prefixes the log file name with the user name associated with the connection and the process ID of the application through which the connection is made. For more information, see [UseLogPrefix](#) on page 114.

## Log Path

| Key Name             | Default Value | Required                    |
|----------------------|---------------|-----------------------------|
| <code>LogPath</code> | None          | Yes, if logging is enabled. |

## Description

The full path to the folder where the connector saves log files when logging is enabled.



**! Important:**

When logging with connection strings and DSNs, this option only applies to per-connection logs.

## Max File Size

| Key Name    | Default Value | Required |
|-------------|---------------|----------|
| LogFileSize | 20971520      | No       |

### Description

The maximum size of each log file in bytes. After the maximum file size is reached, the connector creates a new file and continues logging.

If this property is set using the Windows UI, the entered value is converted from megabytes (MB) to bytes before being set.

**! Important:**

When logging with connection strings and DSNs, this option only applies to per-connection logs.

## Max Number Files

| Key Name     | Default Value | Required |
|--------------|---------------|----------|
| LogFileCount | 50            | No       |

### Description

The maximum number of log files to keep. After the maximum number of log files is reached, each time an additional file is created, the connector deletes the oldest log file.

**! Important:**

When logging with connection strings and DSNs, this option only applies to per-connection logs.

## Mechanism

| Key Name | Default Value                                                                                                       | Required |
|----------|---------------------------------------------------------------------------------------------------------------------|----------|
| AuthMech | No Authentication (0) if you are connecting to Hive Server 1. User Name (2) if you are connecting to Hive Server 2. | No       |

## Description

The authentication mechanism to use.

Select one of the following settings, or set the key to the corresponding number:

- No Authentication ( 0)
- Kerberos (1)
- User Name (2)
- User Name And Password (3)
- Windows Azure HDInsight Service (6)
- SAML\_2.0 (12)

## Minimum TLS

| Key Name | Default Value   | Required |
|----------|-----------------|----------|
| Min_TLS  | TLS 1.2 (1 . 2) | No       |

## Description

The minimum version of TLS/SSL that the connector allows the data store to use for encrypting connections. For example, if TLS 1.1 is specified, TLS 1.0 cannot be used to encrypt connections.

- TLS 1.0 (1 . 0): The connection must use at least TLS 1.0.
- TLS 1.1 (1 . 1): The connection must use at least TLS 1.1.
- TLS 1.2 (1 . 2): The connection must use at least TLS 1.2.

## Password

| Key Name | Default Value | Required                                                                                                   |
|----------|---------------|------------------------------------------------------------------------------------------------------------|
| PWD      | None          | Yes, if the authentication mechanism is User Name And Password (3) or Windows Azure HDInsight Service (6). |

## Description

The password corresponding to the user name that you provided in the User Name field (the `UID` key).

## Port

| Key Name | Default Value                                                                                                                 | Required                                    |
|----------|-------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------|
| Port     | <ul style="list-style-type: none"> <li>non-HDInsight clusters: 10000</li> <li>Windows Azure HDInsight Service: 443</li> </ul> | Yes, if Service Discovery Mode is disabled. |

## Description

The number of the TCP port that the Hive server uses to listen for client connections.

## Proxy Host

| Key Name  | Default Value | Required                                   |
|-----------|---------------|--------------------------------------------|
| ProxyHost | None          | Yes, if connecting through a proxy server. |

## Description

The host name or IP address of a proxy server that you want to connect through.

## Proxy Password

| Key Name | Default Value | Required                                                           |
|----------|---------------|--------------------------------------------------------------------|
| ProxyPWD | None          | Yes, if connecting to a proxy server that requires authentication. |

### Description

The password that you use to access the proxy server.

## Proxy Port

| Key Name  | Default Value | Required                                   |
|-----------|---------------|--------------------------------------------|
| ProxyPort | None          | Yes, if connecting through a proxy server. |

### Description

The number of the port that the proxy server uses to listen for client connections.

## Proxy Username

| Key Name | Default Value | Required                                                           |
|----------|---------------|--------------------------------------------------------------------|
| ProxyUID | None          | Yes, if connecting to a proxy server that requires authentication. |

### Description

The user name that you use to access the proxy server.

## Realm

| Key Name | Default Value                           | Required |
|----------|-----------------------------------------|----------|
| KrbRealm | Depends on your Kerberos configuration. | No       |

### Description

The realm of the Hive Server 2 host.

If your Kerberos configuration already defines the realm of the Hive Server 2 host as the default realm, then you do not need to configure this option.

## Rows Fetched Per Block

| Key Name            | Default Value | Required |
|---------------------|---------------|----------|
| RowsFetchedPerBlock | 10000         | No       |

### Description

The maximum number of rows that a query returns at a time.

Valid values for this setting include any positive 32-bit integer. However, testing has shown that performance gains are marginal beyond the default value of 10000 rows.

## Save Password (Encrypted)

| Key Name | Default Value | Required |
|----------|---------------|----------|
| N/A      | Selected      | No       |

### Description

This option specifies whether the password is saved in the registry.

- Enabled: The password is saved in the registry.
- Disabled: The password is not saved in the registry.

This option is available only in the Windows connector. It appears in the Simba Hive ODBC Connector DSN Setup dialog box and the SSL Options dialog box.

**! Important:**

The password is obscured (not saved in plain text). However, it is still possible for the encrypted password to be copied and used.

## Service Discovery Mode

| Key Name                          | Default Value               | Required |
|-----------------------------------|-----------------------------|----------|
| <code>ServiceDiscoveryMode</code> | No Service Discovery<br>(0) | No       |

### Description

This option specifies whether the connector uses the ZooKeeper service.

- Enabled (1): The connector discovers Hive Server 2 services via the ZooKeeper service.
- Disabled (0): The connector connects to Hive without using a discovery service.

## Service Name

| Key Name                    | Default Value | Required |
|-----------------------------|---------------|----------|
| <code>KrbServiceName</code> | None          | No       |

### Description

The Kerberos service principal name of the Hive server.

## Show System Table

| Key Name                     | Default Value | Required |
|------------------------------|---------------|----------|
| <code>ShowSystemTable</code> | Clear (0)     | No       |

### Description

This option specifies whether the connector returns the `hive_system` table for catalog function calls such as `SQLTables` and `SQLColumns`.

- Enabled (1): The connector returns the `hive_system` table for catalog function calls such as `SQLTables` and `SQLColumns`.
- Disabled (0): The connector does not return the `hive_system` table for catalog function calls.

## Socket Timeout

| Key Name                   | Default Value | Required |
|----------------------------|---------------|----------|
| <code>SocketTimeout</code> | 60            | No       |

## Description

The number of seconds that an operation can remain idle before it is closed.



### Note:

This option is applicable only when asynchronous query execution is being used against Hive Server 2 instances.

## Thrift Transport

| Key Name                     | Default Value                                                                                              | Required |
|------------------------------|------------------------------------------------------------------------------------------------------------|----------|
| <code>ThriftTransport</code> | Binary (0) if you are connecting to Hive Server 1.<br><br>SASL (1) if you are connecting to Hive Server 2. | No       |

## Description

The transport protocol to use in the Thrift layer.

Select one of the following settings, or set the key to the number corresponding to the desired setting:

- Binary (0)
- SASL (1)
- HTTP (2)

**Note:**

For information about how to determine which Thrift transport protocols your Hive server supports, see [Authentication Mechanisms](#) on page 69.

## Trusted Certificates

| Key Name     | Default Value                                                                                                                                                                                                                                                                                                   | Required |
|--------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------|
| TrustedCerts | The <code>cacerts.pem</code> file in the <code>\lib</code> subfolder within the connector's installation directory. The exact file path varies depending on the version of the connector that is installed. For example, the path for the Windows connector is different from the path for the macOS connector. | No       |

### Description

The full path of the `.pem` file containing trusted CA certificates, for verifying the server when using SSL.

If this option is not set, then the connector defaults to using the trusted CA certificates `.pem` file installed by the connector. To use the trusted CA certificates in the `.pem` file, set the `UseSystemTrustStore` property to 0 or clear the Use System Trust Store check box in the SSL Options dialog.

**! Important:**

If you are connecting from a Windows machine and the Use System Trust Store option is enabled, the connector uses the certificates from the Windows trust store instead of your specified `.pem` file.

For more information, see [Use System Trust Store](#) on page 107.



## Two-Way SSL

| Key Name  | Default Value | Required |
|-----------|---------------|----------|
| TwoWaySSL | Clear (0)     | No       |

### Description

This option specifies whether two-way SSL is enabled.

- Enabled (1): The client and the Hive server verify each other using SSL. See also the connector configuration options [Client Certificate File](#) on page 87, [Client Private Key File](#) on page 87, and [Client Private Key Password](#) on page 88.
- Disabled (0): The server does not verify the client. Depending on whether one-way SSL is enabled, the client might verify the server. For more information, see [Enable SSL](#) on page 91.

#### Note:

This option is applicable only when connecting to a Hive server that supports SSL. You must enable SSL before Two Way SSL can be configured. For more information, see [Enable SSL](#) on page 91.

## Unicode SQL Character Types

| Key Name                    | Default Value | Required |
|-----------------------------|---------------|----------|
| UseUnicodeSqlCharacterTypes | Clear (0)     | No       |

### Description

This option specifies the SQL types to be returned for string data types.

- Enabled (1): The connector returns SQL\_WVARCHAR for STRING and VARCHAR columns, and returns SQL\_WCHAR for CHAR columns.
- Disabled (0): The connector returns SQL\_VARCHAR for STRING and VARCHAR columns, and returns SQL\_CHAR for CHAR columns.

## Use Async Exec

| Key Name        | Default Value | Required |
|-----------------|---------------|----------|
| EnableAsyncExec | Clear (0)     | No       |

### Description

This option specifies whether to execute queries synchronously or asynchronously.

- Enabled (1): The connector uses an asynchronous version of the API call against Hive for executing a query.
- Disabled (0): The connector executes queries synchronously.

## Use Native Query

| Key Name       | Default Value | Required |
|----------------|---------------|----------|
| UseNativeQuery | Clear (0)     | No       |

### Description

This option specifies whether the connector uses native HiveQL queries, or converts the queries emitted by an application into an equivalent form in HiveQL. If the application is Hive-aware and already emits HiveQL, then enable this option to avoid the extra overhead of query transformation.

- Enabled (1): The connector does not transform the queries emitted by an application, and executes HiveQL queries directly.
- Disabled (0): The connector transforms the queries emitted by an application and converts them into an equivalent form in HiveQL.

#### ! Important:

When this option is enabled, the connector cannot execute parameterized queries.

## Use Only SSPI

| Key Name    | Default Value | Required |
|-------------|---------------|----------|
| UseOnlySSPI | Clear (0)     | No       |

## Description

This option specifies how the connector handles Kerberos authentication: either with the SSPI plugin or with MIT Kerberos.

- Enabled (1): The connector handles Kerberos authentication by using the SSPI plugin instead of MIT Kerberos by default.
- Disabled (0): The connector uses MIT Kerberos to handle Kerberos authentication, and only uses the SSPI plugin if the GSSAPI library is not available.

### ! Important:

This option is only available on Windows.

## Use Proxy Server

| Key Name | Default Value | Required |
|----------|---------------|----------|
| UseProxy | Clear (0)     | No       |

## Description

This option specifies whether the connector uses a proxy server to connect to the data store.

- Enabled (1): The connector connects to a proxy server based on the information provided in the Proxy Host, Proxy Port, Proxy Username, and Proxy Password fields or the `ProxyHost`, `ProxyPort`, `ProxyUID`, and `ProxyPWD` keys.
- Disabled (0): The connector connects directly to the Hive server.

### Note:

This option is only available on Windows.

## Use System Trust Store

| Key Name            | Default Value | Required |
|---------------------|---------------|----------|
| UseSystemTrustStore | Clear (0)     | No       |

## Description

This option specifies whether to use a CA certificate from the system trust store, or from a specified `.pem` file.

- Enabled (1): The connector verifies the connection using a certificate in the system trust store.
- Disabled (0): The connector verifies the connection using a specified `.pem` file. For information about specifying a `.pem` file, see [Trusted Certificates](#) on page 104.

### ! Important:

If you are connecting from a Windows machine and you want to specify a `.pem` file containing trusted CA certificates, this option must be disabled. For more information, see [Trusted Certificates](#) on page 104.

### Note:

This option is only available on Windows.

## User Name

| Key Name | Default Value                                                                      | Required                                                                                                                                                                |
|----------|------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| UID      | For User Name (2) authentication only, the default value is <code>anonymous</code> | Yes, if the authentication mechanism is User Name And Password (3) or Windows Azure HDInsight Service (6).<br><br>No, if the authentication mechanism is User Name (2). |

## Description

The user name that you use to access Hive Server 2.

## ZK Force Active Passive HA

| Key Name               | Default Value | Required |
|------------------------|---------------|----------|
| ZKForceActivePassiveHA | 0             | No       |

### Description

If the `ZkNamespace` property does not contain "ActivePassiveHA", this option forces the ZooKeeper discovery mode to Active Passive HS2 Interactive HA.

- Enabled (1): The connector enables the Active Passive HS2 Interactive HA mode.
- Disabled (0): The connector does not enable the Active Passive HS2 Interactive HA mode.

#### Note:

This property is ignored if the `ZkNamespace` property contains "ActivePassiveHA".

## ZooKeeper Namespace

| Key Name    | Default Value | Required                                   |
|-------------|---------------|--------------------------------------------|
| ZKNamespace | None          | Yes, if Service Discovery Mode is enabled. |

### Description

The namespace on ZooKeeper under which Hive Server 2 znodes are added.

#### Note:

If the namespace contains "ActivePassiveHA", the connector will enable the Active Passive HS2 Interactive HA connection mode.

## Configuration Options Having Only Key Names

The following configuration options do not appear in the Windows user interface for the Simba Apache Hive ODBC Connector. They are accessible only when you use a connection string or configure a connection from a Linux/macOS/AIX/Solaris machine:

- [ADUserNameCase](#) on page 110
- [DelegationUserIDCase](#) on page 111
- [Driver](#) on page 111
- [ForceSynchronousExec](#) on page 112
- [HTTPAuthCookies](#) on page 112
- [http.header.](#) on page 112
- [SSP\\_](#) on page 114
- [SSOWebServerTimeout](#) on page 113

The `UseLogPrefix` property must be configured as a Windows Registry key value, or as a connector-wide property in the `simba.hiveodbc.ini` file for macOS or Linux.

- [UseLogPrefix](#) on page 114

### ADUserNameCase

| Key Name       | Default Value | Required |
|----------------|---------------|----------|
| ADUserNameCase | Unchanged     | No       |

### Description

This option controls whether the connector changes the user name part of an AD Kerberos UPN to all upper-case or all lower-case. The following values are supported:

- `Upper`: Change the user name to all upper-case.
- `Lower`: Change the user name to all lower-case.
- `Unchanged`: Do not modify the user name.

#### Note:

This option is applicable only when using Active Directory Kerberos from a Windows client machine to authenticate.

## DelegationUserIDCase

| Key Name             | Default Value | Required |
|----------------------|---------------|----------|
| DelegationUserIDCase | Unchanged     | No       |

### Description

This option specifies whether the connector changes the Delegation UID (or `DelegationUID`) value to all upper-case or all lower-case. The following values are supported:

- `Upper`: Change the delegated user name to all upper-case.
- `Lower`: Change the delegated user name to all lower-case.
- `Unchanged`: Do not modify the delegated user name.

For more information about delegating a user name, see [Delegation UID](#) on page 90.

### Driver

| Key Name | Default Value                                                                                                                                                 | Required |
|----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|----------|
| Driver   | Simba Apache Hive ODBC Connector when installed on Windows, or the absolute path of the connector shared object file when installed on a non-Windows machine. | Yes      |

### Description

On Windows, the name of the installed connector (Simba Apache Hive ODBC Connector).

On other platforms, the name of the installed connector as specified in `odbcinst.ini`, or the absolute path of the connector shared object file.

## ForceSynchronousExec

| Key Name             | Default Value | Required |
|----------------------|---------------|----------|
| ForceSynchronousExec | 0             | No       |

### Description

When this option is enabled (1), the connector is forced to execute queries synchronously when connected to an HDInsight cluster.

When this option is disabled (0), the connector is able to execute queries asynchronously when connected to an HDInsight cluster.

#### Note:

This option is applicable only to HDInsight clusters.

## HTTPAuthCookies

| Key Name        | Default Value                    | Required |
|-----------------|----------------------------------|----------|
| HTTPAuthCookies | hive.server2.auth,<br>JSESSIONID | No       |

### Description

A comma-separated list of authentication cookies that are supported by the connector.

If cookie-based authentication is enabled in your server, the connector authenticates the connection once based on the provided authentication credentials. It then uses the cookie generated by the server for each subsequent request in the same connection.

### http.header.

| Key Name     | Default Value | Required |
|--------------|---------------|----------|
| http.header. | None          | No       |



## Description

Set a custom HTTP header by using the following syntax, where *[HeaderKey]* is the name of the header to set and *[HeaderValue]* is the value to assign to the header:

```
http.header.[HeaderKey]=[HeaderValue]
```

For example:

```
http.header.AUTHENTICATED_USER=john
```

After the connector applies the header, the `http.header.` prefix is removed from the DSN entry, leaving an entry of *[HeaderKey]=[HeaderValue]*

The example above would create the following custom HTTP header:

```
AUTHENTICATED_USER: john
```

### Note:

- The `http.header.` prefix is case-sensitive.
- This option is applicable only when you are using HTTP as the Thrift transport protocol. For more information, see [Thrift Transport](#) on page 103.

## SSOWebServerTimeout

| Key Name            | Default Value | Required |
|---------------------|---------------|----------|
| SSOWebServerTimeout | 120           | No       |

## Description

The length of time, in seconds, for which the connector waits for a browser response before timing out. If set to 0, the connector waits for an indefinite amount of time.

### Note:

If `SQL_ATTR_LOGIN_TIMEOUT` is set, `SQL_ATTR_LOGIN_TIMEOUT` takes precedence. The connector honors `SQL_ATTR_LOGIN_TIMEOUT` when using the SAML authentication workflow.

## SSP\_

| Key Name | Default Value | Required |
|----------|---------------|----------|
| SSP_     | None          | No       |

### Description

Set a server-side property by using the following syntax, where *[SSPKey]* is the name of the server-side property and *[SSPValue]* is the value for that property:

```
SSP_[SSPKey]=[SSPValue]
```

For example:

```
SSP_mapred.queue.names=myQueue
```

After the connector applies the server-side property, the SSP\_ prefix is removed from the DSN entry, leaving an entry of *[SSPKey]=[SSPValue]*.

#### Note:

- The SSP\_ prefix must be upper case.
- When setting a server-side property in a connection string, it is recommended that you enclose the value in braces ( { } ) to make sure that special characters can be properly escaped.

## UseLogPrefix

| Key Name     | Default Value | Required |
|--------------|---------------|----------|
| UseLogPrefix | 0             | No       |

### Description

This option specifies whether the connector includes a prefix in the names of log files so that the files can be distinguished by user and application.

Set the property to one of the following values:

- 1: The connector prefixes log file names with the user name and process ID associated with the connection that is being logged.

For example, if you are connecting as a user named "jdoe" and using the connector in an application with process ID 7836, the generated log files would be named `jdoe_7836_simbahiveodbcdriver.log` and `jdoe_7836_simbahiveodbcdriver_connection_[Number].log`, where *[Number]* is a number that identifies each connection-specific log file.

- 0: The connector does not include the prefix in log file names.

To configure this option for the Windows connector, you create a value for it in one of the following registry keys:

- For a 32-bit connector installed on a 64-bit machine: `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Simba\Simba Apache Hive ODBC Connector\Driver`
- Otherwise: `HKEY_LOCAL_MACHINE\SOFTWARE\Simba\Simba Apache Hive ODBC Connector\Driver`

Use `UseLogPrefix` as the value name, and either 0 or 1 as the value data.

To configure this option for a non-Windows connector, you must use the `simba.hiveodbc.ini` file.

## Third-Party Trademarks

Debian is a trademark or registered trademark of Software in the Public Interest, Inc. or its subsidiaries in Canada, United States and/or other countries.

IBM and AIX are trademarks or registered trademarks of IBM Corporation or its subsidiaries in Canada, United States, and/or other countries.

Kerberos is a trademark of the Massachusetts Institute of Technology (MIT).

Linux is the registered trademark of Linus Torvalds in Canada, United States and/or other countries.

Mac, macOS, Mac OS, and OS X are trademarks or registered trademarks of Apple, Inc. or its subsidiaries in Canada, United States and/or other countries.

Microsoft, MSDN, Windows, Windows Azure, Windows Server, Windows Vista, and the Windows start button are trademarks or registered trademarks of Microsoft Corporation or its subsidiaries in Canada, United States and/or other countries.

Red Hat, Red Hat Enterprise Linux, and CentOS are trademarks or registered trademarks of Red Hat, Inc. or its subsidiaries in Canada, United States and/or other countries.

Solaris is a registered trademark of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

SUSE is a trademark or registered trademark of SUSE LLC or its subsidiaries in Canada, United States and/or other countries.

Ubuntu is a trademark or registered trademark of Canonical Ltd. or its subsidiaries in Canada, United States and/or other countries.

Apache Hive, Apache, and Hive are trademarks or registered trademarks of The Apache Software Foundation or its subsidiaries in Canada, United States and/or other countries.

All other trademarks are trademarks of their respective owners.